

0701 CO Weather Station 910401

Use of the application program

Product family: Sensors
 Product type: Weather station
 Manufacturer: Siemens
 Name: AP 257/31 Weather station WS1
 Order no.: 5WG1 257-3AB31

Content overview

| | | |
|-------|---|----|
| 1. | Function overview | 1 |
| 2. | Façades | 1 |
| 2.1. | Number of façades | 1 |
| 2.2. | Façade alignment | 2 |
| 2.3. | Façade inclination | 2 |
| 2.4. | Blind angles | 2 |
| 3. | Behavior at voltage failure / recovery | 3 |
| 4. | Communication objects | 3 |
| 5. | Parameter windows | 7 |
| 5.1. | Location | 7 |
| 5.2. | General adjustments | 8 |
| 5.3. | Functions, Objects | 9 |
| 5.4. | Wind speed | 10 |
| 5.5. | Wind speed limit value x | 10 |
| 5.6. | Brightness | 12 |
| 5.7. | Brightness limit value x | 13 |
| 5.8. | Twilight | 14 |
| 5.9. | Twilight limit value x | 14 |
| 5.10. | Precipitation | 15 |
| 5.11. | Outside temperature | 16 |
| 5.12. | Outside temperature limit value x | 17 |
| 5.13. | Safety | 18 |
| 5.14. | Façade control | 19 |
| 5.15. | Façade x, functions | 19 |
| 5.16. | Façade x, actions | 20 |
| 5.17. | Logic | 22 |
| 5.18. | AND logic operation x, OR logic operation x | 23 |

1. Function overview

In a compact housing, the weather station WS1 (short name: AP 257/31) contains all sensors, the evaluating electronic system and the bus coupling unit. It measures wind speed, brightness and temperature, recognizes twilight and precipitation and receives the DCF77 radio signal for date and time.

In addition to date and time, all measured values can be transmitted on the bus in EIS5 format and respectively monitored on up to 3 limit values. Limit values can be selected as parameters or as communication objects.

Using the "Safety" parameter window, in addition to wind alarm, frost alarm and precipitation alarm, a total of up to 8 alarm or failure messages can be combined via a logical OR-function to a "Safety" communication object, which in the case of alarm results in the sun protection moving into its safety position.

In addition 4 AND-gates and 4 OR-gates with 4 inputs each are available for further logic operations.

The weather station WS1 does not only render possible a simple sun control in which the sun protection is activated or deactivated, depending on whether the sun is shining or not. It can also activate a sun protection control for up to 4 façades under consideration of their alignment (direction of the compass), inclination and blind angles. In this case, the sun protection for a façade is automatically activated only when the sun is shining on the respective façade and deactivated as soon as this is no longer possible or the sun is no longer shining.

This weather station may even be used in places without DCF77 radio reception. In this case date and time have to be received e.g. via the internet and have been transmitted via the bus to the weather station.

The use of the ETS3 Engineering Tool Software is recommended for parameterization and download of data, since it renders possible the best graphic display of the weather station setting menus.

2. Façades

2.1. Number of façades

For façade control the respective alignment of a façade based on the north-south axis and its respective inclination based on the perpendicular on the ground have to be considered. Furthermore, it should be taken into account whether the sun can shine directly from the side and vertically from above onto the façade or whether it can only shine on the façade from a specific angle that is larger than a blind angle predetermined by a wall or roof projection.

Most buildings have 4 façades (see Fig. 1). Since only rarely a façade is aligned exactly northwards, it is rec-

0701 CO Weather station 910401

ommended in principle for the sun protection to be controlled separately for each façade.

If a building has more than 4 façades, the use of an additional weather station AP 257/31 or of the weather station AP 257/21 which can control up to 8 façades, is recommended.

In the case of several buildings, the use of one weather station per building is recommended in principle, since different wind speeds can arise, depending on the location of the buildings with respect to one another.

2.2. Façade alignment

The façade alignment corresponds to the angle between the north-south axis and the perpendicular on the façade (see Fig. 1). The angle α (in the range from 0° to 359°) is hereby measured in clockwise direction (north corresponds to 0°, east 90°, south 180° and west 270°).




Figure 1 Façade alignment

2.3. Façade inclination

If a façade surface is not aligned vertically, this must be taken into account. A forward inclination of the façade is counted as a positive angle, a backward inclination as a negative angle (see Fig. 2).




Figure 2 Façade inclination

The sun protection of windows installed in a sloping roof area can thus also be controlled according to the current position of the sun.

If a façade is not a flat surface, but curved or bent, it must be subdivided into several segments, which must be controlled separately.

2.4. Blind angles

If the sun cannot shine directly from the side and vertically from above onto the façade because this is obstructed by a wall or roof projection, this can be taken into account with the façade control.

Fig. 3 shows how a horizontal blind angle α is measured. With the façade control it is presumed that the horizontal blind angle is the same size on both façade sides. Fig. 4 shows how a vertical blind angle is measured.




Figure 3 Horizontal blind angle




Figure 4 Vertical blind angle

0701 CO Weather station 910401

3. Behavior at voltage failure / recovery

In the event of a supply voltage failure the weather station WS1 does not store any data. Upon recovery of the supply voltage, it records the current sensor data and transmits them. The weather station WS1 then waits for date and time to be updated. As soon as these have been received, without taking into account parameterized waiting times, the actions respectively after the end of the delay period 2 are sent immediately (i.e., with those façades on which the sun is not shining according to the current values of date, time and brightness, at least "Façade x, Sunshine = OFF" is sent and for the others "Façade x, Sunshine = ON").

A bus voltage failure is recognized by the weather station WS1. Data that change after bus voltage failure are stored and transmitted after bus voltage recovery.

4. Communication objects

Maximum number of group addresses: 254
Maximum number of assignments: 254

The following table contains a list of all the available communication objects of the weather station WS1. Which objects are visible in each case and thus transmissible, is determined by the setting of the parameters chosen by the user.

The explanation of the individual objects follows this tabulated overview.

| Nr. | Object name | Function | Number of bits | Flag |
|-----|---------------------------|--------------|----------------|-------|
| 0 | DCF77 date | send | 24 | CRWT |
| 1 | DCF77 time | send | 24 | CRWT |
| 2 | DCF date and time | query | 1 | CRW |
| 3 | Date | receive | 24 | CRWTU |
| 4 | Time | receive | 24 | CRWTU |
| 5 | 8-bit scene | recall | 8 | CRT |
| 6 | Wind sensor, Failure | On / Off | 1 | CRT |
| 7 | Wind speed | actual value | 16 | CRT |
| 10 | Wind, Limit value 1 | set | 16 | CRWTU |
| 11 | Wind alarm | On / Off | 1 | CRT |
| 12 | Wind, Limit value 2 | set | 16 | CRWTU |
| 13 | Wind, Message LV2 | On / Off | 1 | CRT |
| 14 | Wind, Limit value 3 | set | 16 | CRWTU |
| 15 | Wind, Message LV 3 | On / Off | 1 | CRT |
| 16 | Brightness | actual value | 16 | CRT |
| 19 | Brightness, Limit value 1 | set | 16 | CRWTU |
| 20 | Sunshine | On / Off | 1 | CRT |
| 21 | Brightness, Limit value 2 | set | 16 | CRWTU |
| 22 | Brightness, Message LV 2 | On / Off | 1 | CRT |
| 23 | Brightness, Limit value 3 | set | 16 | CRWTU |
| 24 | Brightness, Message LV 3 | On / Off | 1 | CRT |
| 25 | Twilight, Limit value 1 | set | 16 | CRWTU |
| 26 | Darkness | On / Off | 1 | CRT |
| 27 | Twilight, Limit value 2 | set | 16 | CRWTU |
| 28 | Twilight, Message LV 2 | On / Off | 1 | CRT |
| 29 | Twilight, Limit value 3 | set | 16 | CRWTU |

| No. | Object name | Function | Number of bits | Flag |
|-----|-------------------------------------|------------------|----------------|-------|
| 30 | Twilight, Message LV 3 | On / Off | 1 | CRT |
| 31 | Precipitation alarm | On / Off | 1 | CRT |
| 32 | Outside temperature sensor, Failure | On / Off | 1 | CRT |
| 33 | Outside temperature | actual value | 16 | CRT |
| 37 | Temperature, Limit value 1 | set | 16 | CRWTU |
| 38 | Frost alarm | On / Off | 1 | CRT |
| 39 | Temperature, Limit value 2 | set | 16 | CRWTU |
| 40 | Temperature, Message LV 2 | On / Off | 1 | CRT |
| 41 | Temperature, Limit value 3 | set | 16 | CRWTU |
| 42 | Temperature, Message LV 3 | On / Off | 1 | CRT |
| 43 | External alarm | On / Off | 1 | CRW |
| 44 | Safety | On / Off | 1 | CRT |
| 47 | Façade 1, Control | disable / enable | 1 | CRW |
| 48 | Façade 1, Sunshine | On / Off | 1 | CRT |
| 49 | Façade 1, Blind centrally UP / DOWN | UP / DOWN | 1 | CT |
| 50 | Façade 1, Blind centrally DOWN 1 | DOWN 1 | 1 | CT |
| 51 | Façade 1, Blind centrally STEP | UP / DOWN | 1 | CT |
| 52 | Façade 1, Blind position in % | approach | 8 | CT |
| 53 | Façade 1, Slats position in % | approach | 8 | CT |
| 54 | Façade 2, Control | disable / enable | 1 | CRW |
| 55 | Façade 2, Sunshine | On / Off | 1 | CRT |
| 56 | Façade 2, Blind centrally UP / DOWN | UP / DOWN | 1 | CT |
| 57 | Façade 2, Blind centrally DOWN 1 | DOWN 1 | 1 | CT |
| 58 | Façade 2, Blind centrally STEP | UP / DOWN | 1 | CT |
| 59 | Façade 2, Blind position in % | approach | 8 | CT |
| 60 | Façade 2, Slats position in % | approach | 8 | CT |
| 61 | Façade 3, Control | disable / enable | 1 | CRW |
| 62 | Façade 3, Sunshine | On / Off | 1 | CRT |
| 63 | Façade 3, Blind centrally UP / DOWN | UP / DOWN | 1 | CT |
| 64 | Façade 3, Blind centrally DOWN 1 | DOWN 1 | 1 | CT |
| 65 | Façade 3, Blind centrally STEP | UP / DOWN | 1 | CT |
| 66 | Façade 3, Blind position in % | approach | 8 | CT |
| 67 | Façade 3, Slats position in % | approach | 8 | CT |
| 68 | Façade 4, Control | disable / enable | 1 | CRW |
| 69 | Façade 4, Sunshine | On / Off | 1 | CRT |
| 70 | Façade 4, Blind centrally UP / DOWN | UP / DOWN | 1 | CT |
| 71 | Façade 4, Blind centrally DOWN 1 | DOWN 1 | 1 | CT |
| 72 | Façade 4, Blind centrally STEP | UP / DOWN | 1 | CT |
| 73 | Façade 4, Blind position in % | approach | 8 | CT |
| 74 | Façade 4, Slats position in % | approach | 8 | CT |
| 103 | Output AND logic operation 1 | 0 / 1 | 1 | CRT |
| 104 | Output AND logic operation 2 | 0 / 1 | 1 | CRT |
| 105 | Output AND logic operation 3 | 0 / 1 | 1 | CRT |
| 106 | Output AND logic operation 4 | 0 / 1 | 1 | CRT |
| 107 | Output OR logic operation 1 | 0 / 1 | 1 | CRT |
| 108 | Output OR logic operation 2 | 0 / 1 | 1 | CRT |
| 109 | Output OR logic operation 3 | 0 / 1 | 1 | CRT |
| 110 | Output OR logic operation 4 | 0 / 1 | 1 | CRT |

Application program description

April 2009

0701 CO Weather station 910401

| Obj | Object name | Function | Type | Flag |
|--|-------------------|----------|--------|-------|
| 0 | DCF77 date | send | 3 Byte | CRWT |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Date, Time" is set at "Receive via DCF77".</p> <p>The date received by the DCF77 receiver integrated into the weather station is transmitted on the bus via this object.</p> <p><u>Note:</u> After mains recovery / restart it can take several minutes until the date and time are synchronized via the DCF77 receiver. If date and time are requested at the weather station during this time, no telegram will be sent.</p> | | | | |
| 1 | DCF77 time | send | 3 Byte | CRWT |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Date, Time" is set at "Receive via DCF77".</p> <p>The time received by the DCF77 receiver integrated into the weather station is sent on the bus via this object.</p> <p><u>Note:</u> After mains recovery / restart it can take several minutes until date and time are synchronized via the DCF77 receiver. If date and time are requested at the weather station during this time, no telegram will be sent.</p> | | | | |
| 2 | DCF date and time | query | 1 Bit | CRW |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Date, Time" is set at "Receive via DCF77".</p> <p>The transmission of date and time can be requested at the weather station at any time using this object. The telegram content (log. 0 or 1) is hereby irrelevant.</p> | | | | |
| 3 | Date | receive | 3 Byte | CRWTU |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Date, Time" is set at "Receive via the bus".</p> <p>If a DCF77 reception is not possible at the installation site of the weather station, using this object the current date (which is provided, e.g., by a Master clock or over the Internet) can be sent to the weather station to synchronize its software clock. A synchronization after bus or mains failure can take up to 30 s.</p> | | | | |
| 4 | Time | receive | 3 Byte | CRWTU |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Date, Time" is set at "Receive via the bus".</p> <p>If a DCF77 reception is not possible at the installation site of the weather station, using this object the current time (which is provided, e.g., by a Master clock or over the Internet) can be sent to the weather station to synchronize its software clock. The synchronization after bus or mains failure can take up to 30 s.</p> <p><u>Note</u> The time telegram must contain the information of the current day of the week, as otherwise it will not be accepted.</p> | | | | |

| Obj | Object name | Function | Type | Flag |
|--|----------------------------|--------------|--------|-------|
| 5 | 8-bit scene | recall | 1 Byte | CRT |
| <p>Using this object the 8-bit scene with the number x can be recalled. Bit 0...5 hereby contain the scene number. To recall a scene, Bit 7 must be set at log. 0. Bit 6 is currently of no significance and must be set at log. 0.</p> | | | | |
| 6 | Wind sensor, Failure | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Wind speed" is set at "include".</p> <p>A failure of the wind sensor recognized by the weather station is reported via this object.</p> | | | | |
| 7 | Wind speed | Actual value | 2 Byte | CRT |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Wind speed" is set to "include" and in the "Wind speed" parameter window the parameter "Send metered value" is <u>not</u> set to "No".</p> <p>This object is used to transmit the current wind speed as a 16-bit floating point number, optionally with the dimension m/s or km/h.</p> | | | | |
| 10 (12, 14) | Wind, Limit value 1 (2, 3) | set | 2 Byte | CRWTU |
| <p>These objects are visible only if in the "Wind speed" parameter window the relevant parameter "Application of limit value x" is set at "Yes" and in the "Wind speed, limit value x" parameter window the parameter "Limit value adjustment via" is set to "Communication object".</p> <p>Using these objects the respectively associated limit value can be set via the bus to a new value.</p> | | | | |
| 11 | Wind alarm | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Wind speed" parameter window the relevant parameter "Application of limit value x" is set at "Yes".</p> <p>This object is used to report "Wind Alarm = On" as soon as the current wind speed exceeds the limit value 1 and "Wind Alarm = Off" as soon as the current wind speed reaches or falls below the limit value 1 minus hysteresis.</p> | | | | |
| 13 (15) | Wind, Message LV 2 (3) | On / Off | 1 Bit | CRT |
| <p>These objects are visible only if in the "Wind speed" parameter window the relevant parameter "Application of limit value 2 (3)" is set at "Yes".</p> <p>These objects are used to report that the current wind speed has exceeded limit value 2 (or 3) or that the wind speed is again in the permissible range.</p> | | | | |
| 16 | Brightness | Actual value | 2 Byte | CRT |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Brightness" is set at "include" and in the "Brightness" parameter window the parameter "Send metered value" is <u>not</u> set to "No".</p> <p>Using this object the current brightness metered value is transmitted as a 16-bit floating-point number with the dimension "Lux".</p> | | | | |

0701 CO Weather station 910401

| Obj | Object name | Function | Type | Flag |
|---|----------------------------------|----------|--------|-------|
| 19 (21, 23) | Brightness, Limit value 1 (2, 3) | set | 2 Byte | CRWTU |
| <p>These objects are visible only if in the "Brightness" parameter window the relevant parameter "Application of limit value x" is set at "Yes" <u>and</u> in the "Brightness, limit value x" parameter window the parameter "Limit value adjustment via" is set to "Communication object".</p> <p>Using these objects the respectively associated limit value can be set to a new value via the bus.</p> | | | | |
| 20 | Sunshine | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Brightness" parameter window the parameter "Application of limit value 1" is set at "Yes". This object is used to report "Sunshine = On" as soon as the current brightness metered value exceeds the limit value 1 and "Sunshine = Off" as soon as the current brightness metered value reaches or falls below the limit value minus hysteresis.</p> | | | | |
| 22 (24) | Brightness, Message LV 2 (3) | On / Off | 1 Bit | CRT |
| <p>These objects are visible only if in the "Brightness" parameter window the relevant parameter "Application of limit value 2 (3)" is set at "Yes".</p> <p>These objects are used to report that the current brightness metered value has exceeded the limit value 2 (or 3) or that the brightness is again in the permissible range.</p> | | | | |
| 25 (27, 29) | Twilight, Limit value 1 (2, 3) | set | 2 Byte | CRWTU |
| <p>These objects are visible only if in the "Twilight" parameter window the relevant parameter "Application of limit value x" is set at "Yes" <u>and</u> in the "Twilight, limit value x" parameter window the parameter "Limit value adjustment via" is set to "Communication object".</p> <p>These objects can be used to set the respectively associated limit value to a new value via the bus.</p> | | | | |
| 26 | Darkness | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Twilight" parameter window the parameter "Application of limit value 1" is set at "Yes". This object is used to report "Darkness = On" as soon as the current brightness metered value falls below the twilight limit value 1 and "Darkness = Off" as soon as the current brightness metered value reaches or exceeds the limit value 1 plus hysteresis.</p> | | | | |
| 28 (30) | Twilight, Message LV 2 (3) | On / Off | 1 Bit | CRT |
| <p>These objects are visible only if in the "Twilight" parameter window the relevant parameter "Application of limit value 2 (3)" is set at "Yes".</p> <p>These objects are used to report that the current brightness metered value has fallen below the limit value 2 (or 3) or that the brightness is again in the permissible range.</p> | | | | |

| Obj | Object name | Function | Type | Flag |
|---|-------------------------------------|--------------|--------|-------|
| 31 | Precipitation alarm | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Functions, objects" parameter window the parameter "Precipitation alarm" is set at "include".</p> <p>Using this object "Precipitation Alarm = On" is reported as soon as precipitation is detected and "Precipitation Alarm = Off" when it is no longer raining or snowing.</p> | | | | |
| 32 | Outside temperature sensor, Failure | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Functions, objects" parameter window the parameter "Outside temperature" is set at "include".</p> <p>A failure in the temperature sensor recognized by the weather station is reported via this object.</p> | | | | |
| 33 | Outside temperature | Actual value | 2 Byte | CRT |
| <p>This object is visible only if in the "Functions, objects" parameter window the parameter "Outside temperature" is set at "include" <u>and</u> in the "Outside temperature" parameter window the parameter "Send metered value" is <u>not</u> set to "No".</p> <p>Using this object the current outside temperature is transmitted as 16-bit floating point number, optionally with the dimension °C or °F.</p> | | | | |
| 37 (39, 41) | Temperature, Limit value 1 (2, 3) | set | 2 Byte | CRWTU |
| <p>These objects are visible only if in the "Outside temperature" parameter window the relevant parameter "Application of limit value x" is set at "Yes" <u>and</u> in the "Outside temperature, limit value x" parameter window the parameter "Limit value adjustment via" is set to "Communication object".</p> <p>Using these objects the respectively associated limit value can be set to a new value via the bus.</p> | | | | |
| 38 | Frost alarm | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Outside temperature" parameter window the parameter "Application of limit value 1" is set at "Yes".</p> <p>This object is used to report "Frost-Alarm = On" as soon as the current temperature metered value falls below the limit value 1 and "Frost-Alarm = Off," as soon as the current temperature metered value reaches or exceeds the limit value 1 plus hysteresis.</p> | | | | |
| 40 (42) | Temperature, Message LV 2 (3) | On / Off | 1 Bit | CRT |
| <p>These objects are visible only if in the "Outside temperature" parameter window the relevant parameter "Application of limit value 2 (3)" is set at "Yes".</p> <p>These objects are used to report that the current temperature metered value has fallen below (or exceeded) limit value 2 (or 3) and that the outside temperature is once again in the respectively permissible range.</p> | | | | |

Application program description

April 2009

0701 CO Weather station 910401

| Obj | Object name | Function | Type | Flag |
|--|---|--------------------------|-------|------|
| 43 | External alarm | On / Off | 1 Bit | CRW |
| <p>This object is visible only if in the "Safety" parameter window the parameter "Add Object External Alarm" is set at "Yes". Using this object, e.g., a wind alarm message to be additionally applied can be transmitted to the weather station by one or more wind sensors.</p> | | | | |
| 44 | Safety | On / Off | 1 Bit | CRT |
| <p>This object is visible only if in the "Functions, Objects" parameter window the parameter "Safety" is set at "Yes". This object is used to report "Safety = On" when one or more of the alarm messages combined via an OR-function is set at logical 1 and "Safety = Off," when none of the alarm messages is set at logical 1.</p> | | | | |
| 47 (54, 61, 68) | Façade 1 (2, 3, 4), Control | disable / enable (1 / 0) | 1 Bit | CRW |
| <p>These objects are visible only if in the "Façade control" parameter window the parameter "Façade x" is respectively set at "to be used". Using these objects the shade control for each façade can be disabled and enabled separately (e.g. via a time switch program). For disabling a façade control a logical 1 has to be sent via the relevant communication object and for enabling a logical 0. Note: Disabling / enabling the façade control may never be used to prevent a movement of the sun protection. The "movement blockade" object of the sun protection actuators must be used for this! Disabling / enabling the façade control can be used, e.g., to activate the sun protection in summer with enabled sun protection control as soon as the sun shines on the façade. In the winter, on the other hand, the sun protection control can be enabled, e.g., only during the core working hours, in order to thus make it possible for the winter sun to heat the rooms as long as these are not used.</p> | | | | |
| 48 (55, 62, 69) | Façade 1 (2, 3, 4), Sunshine | On / Off | 1 Bit | CRT |
| <p>These objects are visible only if in the "Façade control" parameter window the parameter "Façade x" is respectively set to "to be used". Using these objects "Façade x, Sunshine = On" is transmitted when the sun is shining and the rays of sun could also fall on the respective façade. "Façade x, sunshine = Off" is transmitted when the sun is no longer shining or the rays of sun can no longer fall on the respective façade.</p> | | | | |
| 49 (56, 63, 70) | Façade 1 (2, 3, 4), Blind centrally UP / DOWN | UP / Down | 1 Bit | CT |
| <p>These objects are visible only if in the "Façade x, Actions" parameter window the parameter "Action 2" is set in each case to "Central command DOWN" or to "Central command UP". These objects can be used to move the sun protection for each façade into the upper or lower end position.</p> | | | | |

| Obj | Object name | Function | Type | Flag |
|---|--|-----------|--------|------|
| 50 (57, 64, 71) | Façade 1 (2, 3, 4), Blind centrally DOWN 1 | Down 1 | 1 Bit | CT |
| <p>These objects are visible only if in the "Façade x, Actions" parameter window the parameter "Action 2" is set at "Central Command DOWN 1". Using these objects the sun protection, with drives with 3 limit switches, for each façade can be moved to the lower DOWN 1 end position, in which it then remains with completely opened (i.e., horizontal) slats.</p> | | | | |
| 51 (58, 65, 72) | Façade 1 (2, 3, 4), Blind centrally STEP | Up / Down | 1 Bit | CT |
| <p>These objects are visible only if in the "Façade x, Actions" parameter window the parameter "If brightness, Message LV = Off, Action" is set at "Blind stepwise UP". If the sun is no longer shining on a façade, with this as the first action the sun protection or its slats can be opened by the set number of steps.</p> | | | | |
| 52 (59, 66, 73) | Façade 1 (2, 3, 4), Blind position in % | approach | 1 Byte | CT |
| <p>These objects are visible only if in the parameter window "Façade x, Actions" one of the parameters is set at "Blind position in %". Using this object the movement of the sun blind into the respectively parameterized position is started with the respective façade.</p> | | | | |
| 53 (60, 67, 74) | Façade 1 (2, 3, 4), Slats position in % | approach | 1 Byte | CT |
| <p>These objects are visible only if in the "Façade x, Actions" parameter window one of the parameters is set at "Slats position in %". Using this object the adjustment of the slats into the respectively parameterized position is started with the respective façade.</p> | | | | |
| 103 (104, 105, 106) | Output AND logic operation 1 (2, 3, 4) | 0 / 1 | 1 Bit | CRT |
| <p>These objects are visible only if in the "Logic" parameter window the parameter "AND logic operation x" is respectively set at "active". Using these objects respectively "Output AND logic operation x = On" is sent when the result of the AND combination is a logical 1, and "Output AND logic operation x = Off" is sent when the result of the AND combination is a logical 0.</p> | | | | |

0701 CO Weather station 910401

| Obj | Object name | Function | Type | Flag |
|------------------------------|---------------------------------------|----------|-------|------|
| 107 (108, 109, 110) | Output OR logic operation 1 (2, 3, 4) | 0 / 1 | 1 Bit | CRT |

These objects are visible only if in the "Logic" parameter window the parameter "OR logic operation x" is respectively set to "active".
Using these objects respectively "Output OR logic operation x = On" is sent when the result of the OR combination is a logical 1, and "Output OR logic operation x = Off" is sent when the result of the OR combination is logical 0.

5. Parameter windows

The parameter windows shown below correspond to the ETS3 presentation.

| | |
|-------------------------------------|-----------------------|
| Location | Safety |
| General adjustments | Façade control |
| Functions, Objects | Façade 1, functions |
| Wind speed | Façade 1, actions |
| Wind speed, Limit value 1 (Wind al | Façade 2, functions |
| Wind speed, Limit value 2 | Façade 2, actions |
| Wind speed, Limit value 3 | Façade 3, functions |
| Brightness | Façade 3, actions |
| Brightness, Limit value 1 (Sunshine | Façade 4, functions |
| Brightness, Limit value 2 | Façade 4, actions |
| Brightness, Limit value 3 | Logic |
| Twilight | AND logic operation 1 |
| Twilight, Limit value 1 (Darkness) | AND logic operation 2 |
| Twilight, Limit value 2 | AND logic operation 3 |
| Twilight, Limit value 3 | AND logic operation 4 |
| Precipitation alarm | OR logic operation 1 |
| Outside temperature | OR logic operation 2 |
| Outside temperature, Limit value 1 | OR logic operation 3 |
| Outside temperature, Limit value 2 | OR logic operation 4 |
| Outside temperature, Limit value 3 | |

Fig. 5 Maximum selectable parameter windows

In the delivery state of the weather station (or after a re-setting of all parameters to their default setting) only the 3 parameter windows "Location", "General adjustments" and "Functions, Objects" are visible and thus selectable. Fig. 10 shows the max. selectable parameter windows, when all of the available functions of the weather station have been activated.

5.1. Location

This parameter window is used to set the location of the weather station WS1 as well as, if it cannot be added automatically, when the summer / winter clock changes take place.

If one of the countries listed by name is selected, with a time zone definition corresponding to the UTC standard, the parameters shown in Fig. 6a are visible. The parameters "Summer / winter clock change at" and "Rule for summer / winter clock change" are purely display fields, since the relevant values are set automatically. If one of the cities presented is selected from the parameter "Location," since the location lies in this city or its vicinity, the location coordinates are likewise set automatically and do not need to be determined and entered by the commissioner.

Fig. 6a Location parameters with selectable country and selectable city

If the country in which the weather station has been installed is not included in the selection of countries, the parameters shown in Fig. 6b are visible. Both the "Rule for summer / winter clock change" and the location coordinates must then be entered.

Fig. 6b Location parameters when the country is not selectable

Note: The setting possibilities in bold below correspond to the factory default setting of the parameters.

| Parameter | Settings |
|---|--|
| Country | Germany; Austria; Switzerland; France; Spain; Italy; UK; Netherlands; other countries |
| This parameter is used to select the country in which the weather station has been installed. The subsequent parameters are adjusted depending on the country selected. | |

0701 CO Weather station 910401

| Parameter | Settings |
|--|--|
| Definition of time zone according to | Standard; specific |
| This parameter is used to set whether the summer / winter clock change of the selected country corresponds to the standard there or deviates therefrom (is specific) and therefore has to be set separately. | |
| Summer / winter clock change at | ST: Sun. after March 25th WT: Sun. after Oct 25th |
| This is purely a display field, which is visible only if the previous parameter "Definition of time zone according to" is set at "Standard". This shows that the clock change to summer time occurs on the 1 st Sunday after March 25 and the clock change to winter time on the 1 st Sunday after October 25. | |
| Rule for summer / winter clock change | 03257:0200+0100/10257:0200UTC+0100 |
| This is purely a display field if the parameter "Definition of time zone according to" is set at "Standard" and an input field, if it is set at "specific" or if the parameter "Country" is set at "Other countries". In this case date and time must be entered for the respective clock change and the respective time difference, as explained below: The information up to the slash apply to changing the clock to summer time: "03257" stands for the month (03=March), the date (25) and the day of the week (7=Sunday) and "0200" for the time of the change, "+0100" indicates the number of hours and minutes (1 hour, 0 minutes), by which the previously current winter time is adjusted and "+" the direction of the clock change (+ = set forward). The data after the slash apply to the change to winter time: "10257" stands for the month (10=October), the date (25) and the day of the week (7=Sunday) and "0200" for the time of the switch, and "UTC+0100" indicates the standard time in winter according to the relevant time zone (for Germany, e.g., equal to UTC + 1:00 hour). <u>Note:</u> The data in this field are taken into account for the façade control. Incorrect data lead to an incorrect façade control. | |
| Location | Stuttgart; ... other city |
| This parameter is visible only if a country has been selected, for which one or more locations are offered for selection. If this parameter is set to selectable locations, the relevant longitude and latitude data are automatically adjusted. If none of these locations is relevant and this parameter is therefore set at "other city", the following 4 parameters for entering longitude and latitude information are added. | |
| East. longitude [degree, -180 ...+180] | 0 |
| This parameter is used to set the degrees to the eastern longitude. | |

| Parameter | Settings |
|---|----------|
| East. longitude [minutes, -59...+59] | 0 |
| This parameter is used to set the minutes to the eastern longitude. | |
| North. latitude [degree, -90 ...+90] | 0 |
| This parameter is used to set the degrees to the northern latitude. | |
| north. latitude [minutes, -59...+59] | 0 |
| This parameter is used to set the minutes to the northern latitude. | |

5.2. General adjustments

This parameter window is used to set the cycle times for the cyclic transmission of metered values und logic objects, the transmission delay time after bus and mains voltage recovery and the max. telegram rate.

General adjustments

| | |
|---|--|
| Cycle time for cyclic transmission of metered values | 10 Min. ▼ |
| Cycle time for cyclic transmission of logic objects | 10 Min. ▼ |
| Transmission delay time after bus and mains voltage recovery [in s] | 5 ▲▼ |
| Max. telegram rate [telegrams per second] | 5 ▲▼ |

| Parameter | Settings |
|---|---|
| Cycle time for cyclic transmission of metered values | 5 s; 10 s; 30 s; 1 min; 2 min; 5 min; 10 min ; 20 min; 30 min; 45 min; 1 h |
| This parameter is used to set the joint cycle time for cyclic transmission of date and time and for all metered values with cyclic transmission. | |
| Cycle time for cyclic transmission of logic objects | 5 s; 10 s; 30 s; 1 min; 2 min; 5 min; 10 min ; 20 min; 30 min; 45 min; 1 h |
| This parameter is used to set the joint cycle time for all logic objects with cyclic transmission. | |
| Transmission delay time after bus and mains voltage recovery [in s] | 1...10; 5 |
| This parameter is used to set the delay time that must elapse following the bus or mains voltage recovery before the weather station may again transmit telegrams on the bus. | |
| Max. telegram rate [telegrams per second] | 1...10; 5 |
| This parameter is used to set the maximum number of telegrams the weather station may send on the bus within one second. | |

0701 CO Weather station 910401

5.3. Functions, Objects

This parameter window is used to activate the desired functions of the weather station WS1. These include receiving and optionally transmitting date and time, recording, monitoring and transmitting wind speed, brightness, twilight, precipitation and outside temperature, the logic combination of several objects to the "Safety" object, the shading control for up to 4 façades, depending on the geographic position of the location and the position of the sun, as well as the logic combination of objects of the weather station WS1 by up to 4 AND gates and up to 4 OR gates with up to 4 inputs each. **Note:** The "Twilight" function is available only when the "Brightness" function is set at "include."

The following figure shows the "Functions, Objects" parameter window when all of the functions have been activated.

Functions, Objects

| | |
|-------------------------------------|--------------------------|
| Date, time | receive via DCF77 |
| Send date / time cyclically | Yes |
| Send DCF date and time upon request | at start of a new minute |
| Wind speed | include |
| Brightness | include |
| Twilight | include |
| Precipitation alarm | include |
| Outside temperature | include |
| Safety | Yes |
| Façade control | Yes |
| Logic functions | Yes |

| Parameter | Settings |
|---|--|
| Date, time | receive via DCF77; receive via bus |
| <p>This parameter is used to set whether the weather station should receive the date and time information required via the radio receiver for the time signals of the DCF77 long wave transmitter integrated in the weather station or whether it should receive them via the bus.</p> <p>Note: If a DCF77 reception is not possible at the location of the weather station, the indicator LED for the reception of the DCF77 signal (see Operation and Installation instructions) does not flash regularly once a second. In this case this parameter must be set at "receive via bus" and it must be ensured that a master clock connected to the bus cyclically transmits date and time.</p> <p>If the DCF77 radio reception is temporarily disturbed, date and time will be updated during this time by the software of the weather station (max. divergence 5 s per day).</p> | |

| Parameter | Settings |
|--|---|
| Send date / time cyclically | No; Yes |
| <p>This parameter is visible only if the parameter "Date, time" is set to "receive via DCF77".</p> <p>This parameter is used to set whether the weather station serves as a master clock and should transmit the received date and time information cyclically via the bus. If cyclic transmission is activated, this occurs with the same cycle time with which metered values are also transmitted cyclically (see parameter window "General Settings").</p> | |
| Send DCF date and time upon request | at once; at start of a new minute |
| <p>This parameter is visible only if the parameter "Date, time" is set to "receive via DCF77".</p> <p>This parameter is used to set whether the weather station, after request of date and time through another bus device, transmits this information immediately or if necessary with a delay only after a new minute has started, so that the requesting bus device can also be exactly synchronized with this value.</p> | |
| Wind speed | exclude; include |
| <p>This parameter is used to set whether the weather station should measure and monitor the wind speed. If this parameter is set to "include" the selection option of the "Wind speed" function is added on the left side of the parameter-window of the ETS3.</p> | |
| Brightness | exclude; include |
| <p>This parameter is used to set whether the weather station should measure and monitor brightness. If this parameter is set at "include" the selection options of "Brightness" and of "Twilight" are added on the left side of the parameter window of the ETS3.</p> | |
| Twilight | exclude; include |
| <p>This parameter is visible only if the previous parameter "Brightness" is set to "include."</p> <p>This parameter is used to set whether the measured brightness should be monitored on up to three twilight limit values.</p> | |
| Precipitation alarm | exclude; include |
| <p>This parameter is used to set whether the weather station should record precipitation (rain or snow) or not. If this parameter is set at to "include," the selection option "Precipitation" is added on the left side of the parameter window of the ETS3.</p> | |
| Outside temperature | exclude; include |
| <p>This parameter is used to set whether the weather station should measure and monitor the outside temperature. If this parameter is set at "include," the selection option of the function "Outside temperature" is added on the left side of the parameter window of the ETS3.</p> | |

0701 CO Weather station 910401

| Parameter | Settings |
|---|------------|
| Safety | No; Yes |
| This parameter is used to set whether the weather station should generate the object "Safety" by the logic combination of several objects or not. If this parameter is set to "Yes," the selection option of the function "Safety" is added on the left side of the parameter window of the ETS3. | |
| Façade control | No; Yes |
| This parameter is used to set whether or not the weather station WS1 should carry out a separate Down/Up control of the blinds for each of up to 4 façades. If this parameter is set at "Yes" then the selection options of the function "Façade control" are added on the left side of the parameter window of the ETS3. | |
| Logic functions | No; Yes |
| This parameter is used to set whether up to 4 AND-functions and up to 4 OR-functions with in each case up to 4 inputs should be available at the weather station WS1 or not. Using these logic functions the user can link objects of the weather station WS1 to one another, transmit the result of the logic operation on the bus and, depending on it if set, recall a specific 8-bit scene. If this parameter is set at "Yes" the selection option of the function „Logic“ is added on the left side of the parameter window of the ETS3. | |

5.4. Wind speed

This parameter window is used to set the desired properties of the wind speed measurement and transmission. Moreover, monitoring the wind speed on up to 3 adjustable limit values can be activated. Limit value 1 hereby always serves to detect and transmit the "Wind alarm."

| Wind speed | |
|--|--|
| Send metered value with dimension | <input type="text" value="m/s"/> |
| Metering range, dimension | <input type="text" value="1 ... 70 m/s"/> |
| Send metered value | <input type="text" value="on change of value and cyclically"/> |
| Send after change by % | <input type="text" value="5"/> |
| Detection and storage of max. wind speed | <input type="text" value="Yes"/> |
| Application of limit value 1 | <input type="text" value="Yes"/> |
| Application of limit value 2 | <input type="text" value="Yes"/> |
| Application of limit value 3 | <input type="text" value="Yes"/> |

| Parameter | Settings |
|---|--|
| Send metered value with dimension | m/s; km/h |
| This parameter can be used to adjust whether the metered wind speed should be transmitted on the bus as a 16-bit floating-point number with the dimension "m/s" or converted with the dimension "km/h". | |
| Metering range, dimension | 0 ... 70 m/s |
| This is purely a display field, which gives the metering range of the wind speed, depending on the dimension set via the preceding parameter, either in m/s or in km/h. | |
| Send metered value | No; on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the metered value of the wind speed should be transmitted on the bus. | |
| Send after change by % | 3; 5; 10; 20; 30; 40; 50 |
| This parameter is visible only if the preceding parameter "Send metered value" is set at "on change of value" or at "on change of value and cyclically". | |
| This parameter is used to set the percentage by which the metered value of the wind speed must have changed, before it is sent again on the bus. | |
| Detection and storage of max. wind speed | No; Yes |
| This parameter can be used to activate the recording and storage of the max. wind speed value during a day. The prerequisite for this is that the weather station can receive date and time, in order to thus synchronize its software clock consistently. At the start of a new day (at 00.00.00 hours) the previously stored maximum value is deleted and the current date of the new day is stored. From then on after each measurement a check is carried out of whether the new metered value is greater than the previously stored value and the new value if necessary stored as the max. value together with the current time. At 23.59 the stored max. value together with the information of when it was measured (date and time), is transmitted. Moreover the stored value can be requested at any time with the aid of a special object via the bus, although at the time of query during the day of course it is not ensured that the value then transmitted is indeed the max. value on this day. In the event of a supply voltage failure, the value determined so far is lost. Upon voltage recovery the determination of the max. value begins again. | |
| Application of limit value 1...3 | No; Yes |
| This parameter can be used to activate monitoring of the wind speed on up to 3 different limit values. This is necessary, e.g., when in addition to outside blinds, an outside textile sun protection (e.g. an awning) is installed. If this parameter is set at "Yes," the selection option of the function "Wind speed limit value x" for each activated limit value monitoring is added on the left side of the parameter-window of the ETS3. | |
| Note: The limit value 1 is always used for recording and sending "Wind Alarm". | |

0701 CO Weather station 910401

5.5. Wind speed limit value x

This parameter window is respectively used to set the limit value (LV) at which the metered value (MV) of the wind speed should be monitored and what the reaction should be to exceeding or falling below the respective limit value. Limit value 1 is always used to record and send "Wind Alarm".

Wind speed, Limit value 1 (Wind alarm)

| | |
|--|-----------------------------------|
| Limit value adjustment via | Communication object |
| Limit value 1 (in 0,1 m/s) | 70 |
| Hysteresis 1 (in 0,1 m/s) | 30 |
| ON delay (in seconds) if MV > LV | 3 |
| Action 1 after ON delay | Wind alarm = ON |
| Action 2 after ON delay | recall 8-bit scene |
| Scene number | 1 |
| OFF delay (in minutes) if MV <= LV - Hyst. | 15 |
| Action 1 after OFF delay | Wind alarm = OFF |
| Action 2 after OFF delay | recall 8-bit scene |
| Scene number | 1 |
| Send Wind alarm | on change of value and cyclically |
| Cycle time Wind alarm (in minutes) | 7 |

| Parameter | Settings |
|---|---------------------------------|
| Limit value adjustment via | parameter; communication object |
| This parameter is used to set whether the limit value x should be available as a parameter that can be changed with the ETS or whether a communication object should be added so that the limit value can be changed via the bus. If the limit value setting via a communication object is selected, the factory default parameter value is used for the limit value monitoring until for the first time a limit value is received via the comm. object which then overwrites the factory default parameter value. | |
| Limit value x (in 0,1 m/s) | 1...350; 70 |
| This parameter is used to set the limit value x et as a multiple of 0.1 m/s (setting range 0.1...35 m/s). | |
| Hysteresis x (in 0,1 m/s) | 1...350; 30 |
| This parameter is used to set the hysteresis of the limit value x as a multiple of 0.1 m/s (setting range 0.1...15 m/s). The hysteresis indicates the amount by which the set limit value of the wind speed must be fallen below again after having been exceeded for the "Wind Alarm (or Wind, message LV x) = Off" is sent. | |

| Parameter | Settings |
|--|---|
| ON delay (in seconds) if MV > LV | 0...10; 3 |
| This parameter is used to set by how many seconds the limit value must have been exceeded before "Wind Alarm (or Wind, Message LV x) = On" is transmitted. | |
| Action 1 after ON delay | Wind alarm (resp. Wind, Message LV x) = ON |
| This is purely a display field with the information that after the end of the On delay the communication object "Wind alarm (or Wind, Message LV x)" is sent with the object value "1." | |
| Action 2 after ON delay | not to be applied; recall 8-bit scene |
| This parameter can be used to set whether after the end of the ON delay as a second action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only if the previous parameter "Action 2 after ON delay" is set at "recall 8-bit scene." This parameter can be used to set the number of the desired scene in the range of 1...64. | |
| OFF delay (in minutes) if MV <= LV - Hyst. | 5; 10; 15; 20; 25; 30; |
| This parameter is used to set the number of minutes for which the limit value minus hysteresis must be fallen below, before "Wind Alarm" (or Wind, Message LV x) = Off" is transmitted. | |
| Action 1 after OFF delay | Wind alarm (resp. Wind, message LV x) = OFF |
| This is purely a display field with the information that after the end of the OFF delay the communication object "Wind alarm (or Wind, Message LV x)" is transmitted with the object value "0". | |
| Action 2 after OFF delay | not to be applied; recall 8-bit scene |
| Using this parameter it can be set whether at the end of the Off delay as a second action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action 2 after Off delay" is set to "Recall 8-bit scene". This parameter can be used to set the number of the desired scene in the range of 1...64. | |
| Send wind alarm (resp.: Wind, Message LV x) | on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the object "Wind Alarm (or Wind, Message LV x)" should be sent on the bus. | |

0701 CO Weather station 910401

| Parameter | Settings |
|---|--------------|
| Cycle time Wind alarm (resp. Wind, Message LV x) (in minutes) | 3...15; 7 |
| This parameter is visible only if the previous parameter "Send wind alarm (or Wind, message LV x)" is set at "on change of value and cyclically." Using this parameter the cycle time can be set in the range of 3...15 minutes. | |

5.6. Brightness

This parameter window is used to adjust the desired properties of the brightness measurement and monitoring. Moreover, monitoring the brightness on up to 3 adjustable limit values can be activated.

Brightness

| | |
|--|--|
| Metering range, dimension | <input type="text" value="1 ... 99 kLux"/> |
| Send metered value | <input type="button" value="on change of value and cyclically"/> |
| Send after change by % | <input type="button" value="5"/> |
| Detection and storage of max. brightness | <input type="button" value="Yes"/> |
| Application of limit value 1 | <input type="button" value="Yes"/> |
| Application of limit value 2 | <input type="button" value="Yes"/> |
| Application of limit value 3 | <input type="button" value="Yes"/> |

| Parameter | Settings |
|---|---|
| Metering range, dimension | 0 ... 99 kLux |
| This is purely a display field, indicating the metering range of the brightness. | |
| Send metered value | No; on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the brightness metered value should be sent on the bus. | |
| Send after change by % | 3; 5; 10; 15; 20; 25; 30; 40; 50 |
| This parameter is visible only if the previous parameter "Send metered value" is set at "on change of value" or at "on change of value and cyclically." This parameter is used to set the percentage by which the brightness metered value must have changed before it is sent on the bus again. | |

| Parameter | Settings |
|---|----------|
| Detection and storage of max. brightness | No; Yes |
| This parameter can be used to activate recording and storage of the max. measured brightness during a day. The prerequisite for this is that the weather station can receive date and time in order to thus be able to consistently synchronize its software clock. At the start of a new day (at 00.00.00 hours) the previously stored maximum value is deleted and the current date of the new day is stored. From then on it is tested after each measurement whether the new metered value is greater than the previously stored value and the new value if necessary stored as max. value together with the current time. At 23.59 the stored maximum value together with the information of when it was measured (date and time), is transmitted. Moreover, the stored value can be requested at any time with the aid of a special object via the bus, although at the query time during the day of course it cannot be ensured that the value then transmitted is actually the max. value on this day. In the case of a failure of the supply voltage the value determined so far is lost. After voltage recovery, the determination of the max. value begins again. | |
| Application of limit value 1...3 | No; Yes |
| This parameter can be used to activate the monitoring of the brightness metered value on up to 3 different limit values. This is necessary, e.g., when the measured brightness value is to be used not only for shade control, but also for lighting control. If this parameter is set at "Yes," the selection option of the function "Brightness limit value x" for each activated limit value monitoring is added on the left side of the parameter window of the ETS3. | |
| Note: The limit value 1 is always used for recording and transmitting "Sunshine". | |

0701 CO Weather station 910401

5.7. Brightness limit value x

This parameter window is used to respectively set the limit value to which the brightness metered value should be monitored and what the reaction should be to exceeding the limit value or at the end of exceeding. The limit value 1 is always used for recording and sending "Sunshine."

Brightness, Limit value 1 (Sunshine)

| | |
|--|-----------------------------------|
| Limit value adjustment via | Communication object |
| Limit value 1 (in kLux) | 70 |
| Hysteresis 1 (in kLux) | 10 |
| ON delay if MV > LV | 30 s |
| Action 1 after ON delay | Sunshine = ON |
| Action 2 after ON delay | recall 8-bit scene |
| Scene number | 1 |
| OFF delay 1 (in minutes) if MV <= LV - Hyst. | 5 |
| Action 1 after OFF delay 1 | Sunshine = OFF |
| Action 2 after OFF delay 1 | recall 8-bit scene |
| Scene number | 1 |
| Send Sunshine | on change of value and cyclically |
| Cycle time Sunshine (in minutes) | 7 |

| Parameter | Settings |
|---|---------------------------------|
| Limit value adjustment via | parameter; communication object |
| This parameter is used to set whether the limit value x should be available as a parameter that can be changed only with the ETS or whether a communication object should be added so that the limit value can be changed via the bus. If the limit value setting via a communication object is selected, the factory default parameter value is used for limit value monitoring until for the first time a limit value is received via the comm. object, which then overwrites the factory default parameter value. | |
| Limit value x (in kLux) | 1...99; 70 |
| This parameter is used to set the limit value x in kLux (setting range 1...99 kLux). <u>Note:</u> The limit value 1 always serves for recording and transmitting "Sunshine". | |

| Parameter | Settings |
|---|---|
| Hysteresis x (in kLux) | 1...99; 10 |
| This parameter is used to set the hysteresis of the limit value x in kLux (setting range 1...99 kLux). The hysteresis indicates the amount by which the set brightness limit value must be fallen below again after having been exceeded so that "Sunshine (or Brightness, Message LV x) = Off" is transmitted. | |
| ON delay if MV > LV | 5s; 10s; 15s; 30s; 1 Min.; 2 Min.; 3 Min.; 5 Min. |
| This parameter is used to set how long the limit value must be exceeded before "Sunshine (or Brightness, Message LV x) = On" is sent. | |
| Action 1 after ON delay | Sunshine (resp. Brightness, Message LV x) = ON |
| This is purely a display field with the information that after the end of the ON delay the communication object "Sunshine (or Brightness, Message LV x)" is sent with the object value "1". | |
| Action 2 after ON delay | not to be applied; recall 8-bit scene |
| This parameter can be used to set whether at the end of the ON delay as the second action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action 2 after ON delay" is set at "recall 8-bit scene." Using this parameter the number of the desired scene can be set in the range of 1...64. | |
| OFF delay 1 (in minutes) if MV <= LV - Hyst. | 1...15; 5 |
| This parameter is used to set for how many minutes the limit value minus hysteresis must be fallen below before "Sunshine (or Brightness, Message LV x) = Off" is transmitted. | |
| Action 1 after OFF delay 1 | Sunshine (resp. Brightness, message LV x) = OFF |
| This is purely a display field with the information that after the end of the OFF delay 1 the communication object "Sunshine (or Brightness, Message LV x)" is sent with the object value "0". After this a latency of ca. 2.5 s will always be kept before sending the next telegram. | |
| Action 2 after OFF delay 1 | not to be applied; recall 8-bit scene |
| This parameter can be used to set whether at the end of the OFF delay 1 as the second action an 8-bit Scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only if the previous parameter "Action 2 after OFF delay 1" is set at "recall 8-bit scene." This parameter can be used to set the number of the desired scene in the range from 1...64. | |

Application program description

April 2009

0701 CO Weather station 910401

| Parameter | Settings |
|---|---|
| Send Sunshine (resp. Brightness, Message LV x) | on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the object "Sunshine (or Brightness, Message LV x)" should be sent on the bus. | |
| Cycle time Sunshine (resp. Brightness, Message LV x) (in minutes) | 3...15; 7 |
| This parameter is visible only if the previous parameter "Send sunshine (or Brightness, Message LV x)" is set at "on change of value and cyclically". | |
| This parameter can be used to set the cycle time in the range from 3...15 minutes. | |

5.8. Twilight

This parameter window can be used to activate the monitoring of the brightness metered value on up to 3 adjustable twilight limit values. Limit value 1 is always used for recording and sending "Darkness."

Twilight

Application of limit value 1: Yes

Application of limit value 2: Yes

Application of limit value 3: Yes

| Parameter | Settings |
|--|----------------|
| Application of limit value 1 ... 3 | No; Yes |
| This parameter can be used to activate the monitoring of the brightness metered value on up to 3 different twilight limit values. This is necessary, e.g., when the measured brightness value is to be used not only for sun protection control (lower blinds / shutters in the evening as privacy protection and raise them in the morning) but also as lighting control (switch on exterior lighting in the evening and switch it off in the morning). | |
| If this parameter is set at "Yes," the selection option of the function "Twilight limit value x" for each activated limit value monitoring is added on the left side of the parameter window of the ETS3. | |
| Note: The limit value 1 is always used for recording and sending "Darkness." | |

5.9. Twilight limit value x

This parameter window is used respectively to set to which twilight limit value the brightness metered value should be monitored and what the reaction should be to falling below the limit value or at the end of falling below it. The limit value 1 is always used for recording and sending "Darkness."

Twilight, Limit value 1 (Darkness)

Limit value adjustment via: Communication object

Limit value 1 (in Lux): 200

Hysteresis 1 (in Lux): 10

ON delay if MV < LV: 5 Min.

Action 1 after ON delay: Darkness = ON

Action 2 after ON delay: recall 8-bit scene

Scene number: 1

OFF delay (in minutes) if MV >= LV + Hyst.: 15

Action 1 after OFF delay: Darkness = OFF

Action 2 after OFF delay: recall 8-bit scene

Scene number: 1

Send Darkness: on change of value and cyclically

Cycle time Darkness (in minutes): 7

| Parameter | Settings |
|--|---|
| Limit value adjustment via | parameter; communication object |
| This parameter is used to set whether the limit value x should be available as a parameter that can be changed only with the ETS or whether a communication object should be added so that the limit value can be changed via the bus. | |
| If the limit value setting is selected via a communication object, the factory default parameter value is used for limit value monitoring until for the first time a limit value is received by the comm. object that exceeds the factory default parameter value. | |
| Limit value x (in Lux) | 1...1000; 200 |
| This parameter is used to set the limit value x in Lux (setting range 1...1000 Lux). | |
| Hysteresis x (in Lux) | 1...99; 10 |
| This parameter is used to set the hysteresis of the limit value in Lux (setting range 1...99 Lux). The hysteresis indicates the amount by which the set twilight limit value after having been fallen below must then be exceeded again for "Darkness" (or twilight, Message LV x) =OFF" to be sent. | |

0701 CO Weather station 910401

| Parameter | Settings |
|--|---|
| ON delay if MV < LV | 5s; 10s; 15s; 30s; 1 Min.; 2 Min.; 3 Min.; 5 Min. |
| This parameter is used to set how long the twilight limit value must be fallen below before "Darkness (or Twilight, Message LV x) = ON" is sent. | |
| Action 1 after ON delay | Darkness (resp. Twilight, message LV x) = ON |
| This is purely a display field with the information that after the ON delay the communication object "Darkness (or Twilight, Message LV x)" is sent with the object value "1." | |
| Action 2 after ON delay | not to be applied; recall 8-bit scene |
| This parameter can be adjusted whether at the end of the ON delay as the second action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action 2 after ON delay" is set at "recall 8-bit scene." Using this parameter the number of the desired scene can be set in the range of 1...64. | |
| OFF delay (in minutes) if MV >= LV + Hyst. | 1...15; 15 |
| This parameter is used to set how many minutes the limit value plus hysteresis must be exceeded before "Darkness (or Twilight, Message LV x) = Off" is sent. | |
| Action 1 after OFF delay | Darkness (or twilight, message LV x) = OFF |
| This is purely a display field with the information that after the end of the OFF delay the communication object "Darkness (or Twilight, Message LV x)" is sent with the object value "0." | |
| Action 2 after OFF delay | not to be applied; recall 8-bit scene |
| This parameter can be used to set whether at the end of the OFF delay as second action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only if the previous parameter "Action 2 after OFF delay" is set at "recall 8-bit scene." Using this parameter the number of the desired scene can be set in the range from 1...64. | |
| Send Darkness (resp. Twilight, Message LV x) | on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the object "Darkness (or Twilight, Message LV x)" should be sent on the bus. | |

| Parameter | Settings |
|---|------------------|
| Cycle time Darkness (resp. Twilight, Message LV x) (in minutes) | 3...15; 7 |
| This parameter is visible only when the previous parameter "Send darkness (or Twilight, Message LV x)" is set at "on change of value and cyclically." This parameter can be used to set the cycle time in the range from 3...15 minutes. | |

5.10. Precipitation

This parameter window is used to set when the object "Precipitation alarm" should be sent and whether an additional action should be carried out with "Precipitation alarm = ON" or with "Precipitation alarm = Off."
Note: The delay times with the recognition of precipitation are fixed and cannot be changed by the user.

Precipitation alarm

Send Precipitation alarm ON / OFF on change of value and cyclically

Cycle time Precipitation alarm (in minutes) 7

Action if Precipitation alarm = ON recall 8-bit scene

Scene number 1

Action if Precipitation alarm = OFF recall 8-bit scene

Scene number 1

| Parameter | Settings |
|---|---|
| Send Precipitation alarm ON / OFF | on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the object "Precipitation alarm" should be sent on the bus. | |
| Cycle time Precipitation alarm (in minutes) | 3...15; 7 |
| This parameter is visible only when the previous parameter "Send Precipitation alarm ON / OFF" is set at "on change of value and cyclically". This parameter can be used to set the cycle time in the range of 3...15 Minutes. | |
| Action if Precipitation alarm = ON | not to be applied; recall 8-bit scene |
| This parameter can be used to set whether with "Precipitation alarm = ON" as an additional action an 8-bit scene should be recalled. | |

0701 CO Weather station 910401

| Parameter | Settings |
|--|---------------------------------------|
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action if "Precipitation Alarm = ON" is set at "recall 8-bit scene". | |
| This parameter can be used to set the number of the desired scene in the range of 1...64. | |
| Action if Precipitation alarm = OFF | not to be applied; recall 8-bit scene |
| This parameter can be used to set whether with "Precipitation alarm = OFF" as additional action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action if Precipitation alarm = OFF" is set at "recall 8-bit scene". | |
| This parameter can be used to set the number of the desired scene in the range of 1...64. | |

5.11. Outside temperature

This parameter window is used to set the desired properties of the temperature measurement and transmission. Furthermore, the monitoring of the temperature on up to 3 adjustable limit values can be activated. Limit value 1 is always used for recording and sending "Frost-Alarm."

Outside temperature

| | |
|--|-----------------------------------|
| Send metered value with dimension | °C |
| Metering range, dimension | -40 ... +80 °C |
| Temperature offset (in 0.1 K) | 0 |
| Send metered value | on change of value and cyclically |
| Send after change by | 1.0 K |
| Detection and storage of min. / max. temperature | Yes |
| Application of limit value 1 | Yes |
| Application of limit value 2 | Yes |
| Application of limit value 3 | Yes |

| Parameter | Settings |
|--|-----------|
| Send metered value with dimension | °C; °F |
| This parameter can be used to set whether the measured outside temperature should be sent on the bus as a 16-bit floating point number with the dimension "°C" or converted with the dimension "°F." | |

| Parameter | Settings |
|---|---|
| Metering range, dimension | -40 ... +80 °C |
| This is purely a display field that indicates the metering range of the outside temperature. | |
| Temperature offset (in 0,1 K) | -50 ... +50; 0 |
| This parameter can be used to change the metered value by an adjustable offset value, in order to thus align it e.g., with a calibrated thermometer. | |
| Send metered value | No; on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the temperature metered value should be sent on the bus. | |
| Send after change by | 0,5 K; 1,0 K; 2,0 K |
| This parameter is visible only when the previous parameter "Send metered value" is set at "on change of value" or at "on change of value and cyclically." | |
| This parameter is used to set by how many degrees Kelvin the temperature metered value must have changed before it is sent again on the bus. | |
| Detection and storage of min. / max. temperature | No; Yes |
| This parameter can be used to activate the recording and storage of the minimum and maximum measured temperature during a day. The prerequisite for this is that the weather station can receive the date and time in order to thus consistently synchronize its software clock. | |
| At the start of a new day (at 00.00.00 hours) the previously stored minimum and maximum value are deleted and the current date of the new day is stored. From then on a test is carried out after each measurement whether the new metered value is greater than the previously stored maximum value or lower than the previously stored minimum value and, if applicable, the new value is stored as the min. or max. value together with the current time. At 23.59 the stored min. and max. value together with the information of when they were measured in each case (date, time), are transmitted. Furthermore, the stored values can be requested at any time with the aid of a special object via the bus, although it cannot be ensured at the query time during the day that the values then transmitted are actually the min. and max. value on this day. In the case of failure of the supply voltage the values determined so far are lost. After voltage recovery the determination of the min. / max. value starts again. | |
| Application of limit value 1 ... 3 | No; Yes |
| This parameter can be used to activate the monitoring of the outside temperature on up to 3 different limit values. This is necessary, e.g., when the outside temperature is to be monitored not only via the limit value 1 for a frost limit. | |
| If this parameter is set at "Yes," the selection option of the function "Outside temperature limit value x" for each activated limit value monitoring is added on the left side of the parameter window of the ETS3. | |

0701 CO Weather station 910401

5.12. Outside temperature limit value x

This parameter window is respectively used to set the limit value at which the outside temperature should be monitored, and what the reaction should be to falling below or exceeding the respective temperature limit value. **Note:** The outside temperature limit value 1 is set by factory default as frost protection limit value, i.e., as a limit value that is monitored for falling below. However, with the outside temperature limit values 2 and 3 it can be selected whether the temperature should be monitored for a lower or an upper limit value.

Outside temperature, Limit value 1 (Frost alarm)

| | |
|-------------------------------------|-----------------------------------|
| Limit value adjustment via | Communication object |
| Limit value 1 (in 0.5 K) | 2 |
| Hysteresis 1 (in 0.5 K) | 6 |
| Frost alarm | ON if MV<LV / OFF if MV>=LV+Hyst. |
| ON-delay | 10 Min. |
| Action if Frost alarm = ON | recall 8-bit scene |
| Scene number | 1 |
| OFF-delay | 10 Min. |
| Action if Frost alarm = OFF | recall 8-bit scene |
| Scene number | 1 |
| Send Frost alarm | on change of value and cyclically |
| Cycle time Frost alarm (in minutes) | 7 |

| Parameter | Settings |
|---|---|
| Limit value adjustment via | parameter; communication object |
| This parameter is used to set whether the limit value x should be available as a parameter that can be changed only with the ETS or whether a communication object should be added so that the limit value can be changed via the bus. If the limit value setting is selected via a communication object, the factory default parameter value is used for limit value monitoring until for the first time a limit value is received via the comm. object that then overwrites the factory default parameter value. | |
| Limit value x (in 0.5 K) | -80 ... +160; 2 |
| This parameter is used to set the limit value x as a multiple of 0.5 °C (Setting range -40...+80 °C). Note: The limit value 1 for outside temperature is set by the factory as a frost protection limit value at +1 °C. | |

| Parameter | Settings |
|---|--|
| Hysteresis x (in 0.5 K) | 1...20; 6 |
| This parameter is used to set the hysteresis of the limit value x as a multiple of 0.5 degrees Kelvin (setting range 0.5...10 K). The hysteresis indicates the amount by which the set temperature limit value must be exceeded again after having been fallen below or after being exceeded, fallen below again) so that "Frost-Alarm (or Temperature, Message LV x =) Off" is sent. | |
| Frost alarm | ON if MV < LV / OFF if MV >= LV + Hyst. |
| With outside temperature limit value 1 this is purely a display field with the information that the temperature limit value 1 is monitored for a lower limit value (the frost limit value) and that after this limit value has been fallen below the communication object "Frost alarm" is sent with the object value "1" and that after this limit value has been exceeded plus hysteresis the communication object "Frost alarm" is sent with the object value "0." | |
| Temperature, Message LV x | ON if MV<LV / OFF if MV>=LV+Hyst.; ON if MV>LV / OFF if MV<=LV-Hyst. |
| With outside temperature limit values 2 and 3 it is adjustable whether they are to be monitored for a lower limit value (ON when MV<LV / Off when MV>=LV+Hyst.) or for an upper limit value (ON when MV>LV / OFF when MV<=LV-Hyst.). | |
| ON-delay | 1s; 3s; 5s; 10s; 15s; 30s; 1 Min.; 2 Min.; 3 Min.; 5 Min.; 10 Min.; 15 Min.; 30 Min.; 1 h |
| This parameter is used to set how long the temperature limit value, has to be fallen below (or exceeded) before "Temperature, Message LV x = ON" is sent. | |
| Action if Frost alarm (resp. Temperature, Message LV x) = ON | not to be applied; recall 8-bit scene |
| It can be adjusted via this parameter whether at the end of the ON delay as an additional action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action if Frost alarm (or Temperature, Message LV x) = ON" is set at "recall 8-bit scene". This parameter can be used to set the number of the desired scene in the range from 1...64. | |
| OFF-delay | 1s; 3s; 5s; 10s; 15s; 30s; 1 Min.; 2 Min.; 3 Min.; 5 Min.; 10 Min.; 15 Min.; 30 Min.; 1 h |
| This parameter is used to set how long falling below (or exceeding) the limit value must have been completed taking into account the hysteresis so that "Frost alarm (or Temperature, Message LV x) = OFF" is sent. | |

0701 CO Weather station 910401

| Parameter | Settings |
|--|--|
| Action if Frost alarm (or Temperature, Message LV x) = OFF | not to be applied; recall 8-bit scene |
| This parameter can be used to set whether at the end of the OFF delay as an additional action an 8-bit scene should be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action if Frost alarm (or Temperature, Message LV x) = OFF" is set at "recall 8-bit scene". This parameter can be used to set the number of the desired scene in the range of 1...64. | |
| Send Frost alarm (resp. Temperature, Message LV x) | on change of value; on change of value and cyclically |
| This parameter is used to set whether or when the object "Frost alarm (or Temperature, message LV x)" should be sent on the bus. | |
| Cycle time Frost alarm (resp. Temperature, Message LV x) (in minutes) | 3...15; 7 |
| This parameter is visible only when the previous parameter "Send Frost alarm (or Temperature, message LV x)" is set at "on change of value and cyclical." Using this parameter the cycle time can be set in the range from 3...15 minutes. | |

5.13. Safety

Using this parameter window up to 8 alarm objects can be logically combined via an OR function to the object "Safety."

Note: Usually with the object "Safety" at the addressed sun protection actuators a movement into the safety position is triggered (e.g. the upper end position) and leaving this end position is blocked as long as the object "Safety" has the logical value "1."

Safety

Add object External alarm: Yes

If: Wind alarm = ON

OR: Wind, Message LV 2 = ON

OR: Wind, Message LV 3 = ON

OR: Precipitation alarm = ON

OR: Frost alarm = ON

OR: External alarm = ON

OR: Wind sensor, Failure = ON

OR: Output OR logic operation 1 = ON

then: Safety = ON

Send Safety: on change of value and cyclically

Cycle time Safety (in minutes): 7

| Parameter | Settings |
|--|--|
| Add object External alarm | No; Yes |
| If this parameter is set at "Yes," an object "External alarm" is added to the communication objects via which e.g., a wind alarm can be received from an additional wind sensor. | |
| If: | not to be applied; Wind alarm = ON |
| This parameter is used to set whether the object "Wind alarm" with the logical value "1" should be combined via this OR function to the safety object. | |
| OR | not to be applied; Wind, Message LV 2 = ON |
| This parameter is used to set whether the object "Wind, Message LV 2" with the logical value "1" should be combined via this OR function to the safety object. | |
| OR | not to be applied; Wind, Message LV 3 = ON |
| This parameter is used to set whether the object "Wind, Message LV3" with the logical value "1" should be combined via this OR function to the safety object. | |
| OR | not to be applied; Precipitation alarm = ON |
| This parameter is used to set whether the object "Precipitation alarm" with the logical value "1" should be combined via this OR function to the safety object. | |
| OR | not to be applied; Frost alarm = ON |
| This parameter is used to set whether the object "Frost alarm" with the logical value "1" should be combined via this OR function to the safety object. | |

0701 CO Weather station 910401

| Parameter | Settings |
|--|--|
| OR | not to be applied; External alarm = ON |
| This parameter is used to set whether the object "External alarm" with the logical value "1" should be combined via this OR function to the safety object. | |
| OR | not to be applied; Wind sensor, Failure = ON |
| This parameter is used to set whether the object "Wind sensor, Failure" with the logical value "1" should be combined via this OR function to the safety object. | |
| OR | not to be applied; Output OR logic operation 1 = ON; Output OR logic operation 2 = ON; Output OR logic operation 3 = ON; Output OR logic operation 4 = ON; Output AND logic oper. 1 = ON; Output AND logic oper. 2 = ON; Output AND logic oper. 3 = ON; Output AND logic oper. 4 = ON |
| This parameter is used to set whether one of the output objects of the 4 OR functions or the 4 AND functions with the logical value "1" should be combined via this OR function to the safety object. | |
| then: | Safety = ON |
| This is purely a display field. It shows that the object "Safety" is sent with the logical value "1" when the set conditions of the logical OR function have been met. | |
| Send Safety | on change of value; on change of value and cyclically |
| This parameter is used to set when the object "Safety" should be sent on the bus. | |
| Cycle time Safety (in minutes) | 3...15; 7 |
| This parameter is visible only when the previous parameter "Send Safety" is set at "on change of value and cyclically." This parameter can be used to set the cycle time in the range of from 3...15 minutes. | |

5.14. Façade control

This parameter window can be used to activate the desired number of façade controls.

Façade control

| | |
|----------|------------|
| Façade 1 | to be used |
| Façade 2 | to be used |
| Façade 3 | to be used |
| Façade 4 | to be used |

| Parameter | Settings |
|--|--------------------------------------|
| Façade x | not to be used; to be used |
| If this parameter is set at "to be used," the selection link for "Façade x, functions" and "Façade x, actions" for each façade used is added on the left side of the parameter window of the ETS3. | |

5.15. Façade x, functions

Using this parameter window for each façade the characteristic values (alignment, inclination, blind angle) are entered and determined which communication object (or which command) is to be transmitted to lower the sun protection as soon as the sun begins to shine on the façade and to raise the sun protection as soon as the sun can no longer shine on the façade.

Façade 1, functions

| | |
|--|--------------------------------------|
| Orientation (North=0°, E=90°, S=180°, W=270°) | 0 |
| Inclination (against base point of vertical) | 0 |
| Blind angle horizontal | 2 |
| Blind angle vertical | 2 |
| Shading control via | Brightness, Limit value 1 (Sunshine) |
| OFF delay 2 in minutes if Brightness, Message LV = OFF | 10 |
| Façade 1, send Sunshine | on change of value and cyclically |
| Cycle time façade 1 in minutes: | 15 |

| Parameter | Settings |
|--|--------------|
| Orientation (North=0°, E=90°, S=180°, W=270°) | 0...359; 0 |
| Using this parameter analogously to the wind rose, the direction is entered in which the vertical shows on the façade surface or, with a sloping roof, the direction in which the vertical would show on the sloping roof set vertically. North is hereby 0°, east 90°, etc. | |
| Inclination (against base point of vertical) | -89...+60; 0 |
| This parameter is used to enter by how many degrees the façade surface is tilted with respect to the base point of vertical. A forward inclination of the façade is counted as positive here, a backward inclination as negative. Roofs therefore have a negative inclination (-90° corresponds to a flat roof). | |

Application program description

April 2009

0701 CO Weather station 910401

| Parameter | Settings |
|--|--|
| Blind angle horizontal | 2...25; 2 |
| <p>This parameter is used to set whether the sun protection should be activated immediately when the sun begins to shine on the façade from the side (horizontal blind angle > 0°) or whether it should be activated later when the rays of the sun fall on the façade at an angle that is greater than the set horizontal blind angle. A blind angle occurs, e.g., through a lateral projection (wall projection).</p> <p><u>Note:</u> The horizontal blind angle set is presumed to be the same size on both sides (i.e. the same size both on the right and on the left side of the façade).</p> | |
| Blind angle vertical | 2...45; 2 |
| <p>This parameter is used to set whether the sun protection should be activated immediately when the sun begins to shine on the façade vertically from above (vertical blind angle > 0°) or whether it should be activated somewhat later because, e.g., the roof projects somewhat and the rays of the sun do not fall onto the façade until the vertical blind angle is exceeded.</p> | |
| Shading control via | Brightness Limit value 1 (Sunshine); Brightness, Limit value 2; Brightness, Limit value 3 |
| <p>This parameter is used to establish which of the 3 brightness limit values (or which object "brightness, Message LV x = ON/OFF") should be applied in calculating whether the sun is shining on the current façade.</p> | |
| OFF delay 2 in minutes if Brightness, Message LV = OFF | 1...15; 10 |
| <p>So that the sun protection of the façade is not immediately raised when sunshine is interrupted by a cloud, with the Off delay 2 a further delay time can be taken into consideration at the start of which e.g. the slats are placed horizontally for max. admission of light. When it is over, first the end of the sunshine is reported for the current façade and then the sun protection is raised.</p> | |
| Façade x, send Sunshine | on change of value; on change of value and cyclically |
| <p>This parameter is used to set when the object "Façade x, Sunshine" should be sent on the bus.</p> | |
| Cycle time façade x in minutes | 5...60; 15 |
| <p>This parameter is visible only when the previous parameter "Façade x, send Sunshine" is set at "on change of value and cyclically."</p> <p>This parameter can be used to set the cycle time in the range from 5...60 minutes</p> | |

5.16. Façade x, actions

This parameter window is used for each façade to set which commands are to be sent as soon as the sun shines on the façade and when the sun is no longer shining or can no longer shine on the façade.

Note: The object "Façade x, Sunshine = OFF" is sent without delay as soon as the sun can no longer shine on the façade x.

Façade 1, actions

If Brightness, Message LV = ON,

Action 1:

Action 2:

If Brightness, Message LV = OFF,

Action:

Number of steps:

After OFF delay 2,

Action 1:

Action 2:

| Parameter | Settings |
|---|--------------------------------|
| If Brightness, Message LV = ON, Action 1 | Façade x, Sunshine = ON |
| <p>This is purely a display field. It contains the message that if the brightness limit value selected for this façade is exceeded (i.e., the sun is indeed shining) and moreover the sun has reached a position from which it can shine on this façade, the object "Façade x, Sunshine" is sent with the object value "1." This telegram can be used to lower (activate) the entire sun protection for this façade.</p> <p>If action 1 is followed by an action 2, the sending of the first telegram of action 2 will take place after a latency of ca. 2.5 s.</p> | |

0701 CO Weather station 910401

| Parameter | Settings |
|--|--|
| Action 2 | not to be applied; Central command DOWN; Central command DOWN1; Blind position in %; Blind + slats position in %; recall 8-bit scene |
| <p>- Central command DOWN: The object "Façade x, blind centrally UP/DOWN" with the object value "1" is sent once. With Siemens actuators this is to be linked with the object "Channels A-X, Automatic operation = On + centrally Up/ Down." Through this firstly all the actuator channels are switched to automatic operation and then the addressed sun protection is moved into the lower end position. It is thus ensured that with the start of sunshine all the sun protection devices of the façade concerned will be lowered and all the channels will be in automatic operation, as long as the occupant of the room does not disable the automatic operation for the sun protection devices that he can control.</p> <p>- Central command DOWN1: The object "Façade x, Blind centrally DOWN1" with the object value "1" is sent once, via which all the actuator channels are switched to automatic operation and the addressed sun protection drives with 3 limit switches are moved into the DOWN1 end position with opened slats. (Warning: This command can be used only with blind actuators that can control drives with 3 limit switches!)</p> <p>- Blind position in %: The object "Façade x, Blind position in %" is sent once with an object value that is determined via the parameter subsequently shown with this setting.</p> <p>- Blind + slats position in %: The objects "Façade x, Blind position in %" and "Façade x, Slats position in %" are sent once with an object value that is determined via the parameter subsequently shown in each case.</p> <p>- Recall 8-bit scene: The object "8-bit scene" is sent once with a scene number that is established via the parameter subsequently shown.</p> | |
| Blind position in % | 50...100; 100 |
| <p>This parameter is visible only when the previous parameter "Action 2" is set to "Blind position in %" or to "Blind + slats position in %".</p> <p>It is used to set in the range of 50...100% how far the sun protection should be closed (100% = completely closed).</p> | |
| Slats position in % | 50...100; 100 |
| <p>This parameter is visible only when the previous parameter "Action 2" is set at "Blind + slats position in %".</p> <p>It is used to set in the range of from 50...100% how far the slats are to be closed (100% = completely closed).</p> | |
| Scene number | 1...64; 1 |
| <p>This parameter is visible only when the previous parameter "Action 2" is set to "Recall 8-bit scene."</p> <p>This parameter can be used to set the number of the desired scene in the range from 1...64.</p> | |


| Parameter | Settings |
|--|--|
| If Brightness, Message LV = OFF, Action | not to be applied; blind stepwise UP; slats position in % |
| <p>If the sun is no longer shining and it has therefore fallen below the brightness limit value used for the control of the façade minus hysteresis, at the end of the OFF delay 1 the object "Brightness, Message LV x" is sent with the object value "0."</p> <p>With activated façade control this parameter can be used to set whether there should be a reaction to this event and what it should be.</p> <p>- Not to be applied: There is no reaction, instead a wait in case the sunshine may return during the OFF delay 2.</p> <p>- Blind stepwise UP: If shutters are used as sun protection, they can now be raised by an adjustable number of steps. The shutter slats and the shutters themselves are opened somewhat so that a little more daylight reaches the rooms.</p> <p>- Slats position in %: If Venetian blinds are used as sun protection, their slats can be opened halfway to completely so that more daylight reaches the rooms.</p> | |
| Number of steps | 1...7; 3 |
| <p>This parameter is visible only when the previous parameter "If brightness, Message LV = OFF, Action" is set at "Blind stepwise UP."</p> <p>This parameter can be used to set by how many steps the sun protection should be raised after the end of OFF delay 1, when the sun is no longer shining.</p> | |
| Slats position in % | 0...50; 0 |
| <p>This parameter is visible only if the previous parameter "If brightness, Message LV = OFF, Action" is set to "slats position in %."</p> <p>This parameter is used to set in the range from 0...50% how far after the end of the Off delay 1, when the sun is no longer shining, the slats should be opened (0% = completely opened = horizontal position of the horizontal slats of Venetian blinds).</p> | |

0701 CO Weather station 910401

| Parameter | Settings |
|--|--|
| After OFF delay 2, Action 1 | not to be applied; central command UP; blind position in %; blind + slats position in %; recall 8-bit scene |
| <p>This parameter can be used to set (when the sun is still not shining after the end of the OFF delay 2) whether another command object should be transmitted and if so, which one.</p> <ul style="list-style-type: none"> - Central command UP: The object "Façade x, Blind centrally UP/DOWN" is sent once with the object value "0". If necessary, this object is to be linked with Siemens actuators with their object "Channels A-X, Automatic operation=On + central Up/Down". With the actuators thus firstly all the channels are switched to automatic operation and then the addressed sun protection is moved into the upper end position. It is thus ensured that at the end of sunshine all of the sun protection devices of the façade concerned are raised and all channels are again in automatic operation. - Blind position in %: The object "Façade x, Blind position in %" is sent once with an object value that is established via the parameter subsequently shown with this setting. - Blind + slats position in %: The objects "Façade x, Blind position in %" and "Façade x, Slats position in %" are sent once with an object value that is established in each case via the parameter subsequently shown. - Recall 8-bit scene: This object is sent once with a scene number that is stipulated via the parameter subsequently shown. | |
| Blind position in % | 0...100; 0 |
| <p>This parameter is visible only if the previous parameter "After OFF delay 2, Action 1" is set to "Blind position in %" or to "Blind + slats position in %."</p> <p>It is used to set in a range from 0...100% how far the sun protection is to be opened (0% = completely opened).</p> | |
| Slats position in % | 0...100; 0 |
| <p>This parameter is visible only if the previous parameter "After OFF delay 2, Action 1" is set at "Blind + slats position in %."</p> <p>It is used to set in a range from 0...100% how far the slats are to be opened (0% = completely opened).</p> | |
| Scene number | 1...64; 1 |
| <p>This parameter is visible only if the previous parameter "After OFF delay 2, Action 1" is set at "recall 8-bit scene."</p> <p>With this parameter the number of the desired scene can be set in the range of 1...64.</p> | |
| Action 2 | Façade x, Sunshine = OFF |
| <p>This is purely a display field. It contains the message that if the sun is still not shining after the end of the OFF delay 2, the object "Façade x, Sunshine" will be transmitted with the object value "0." This telegram can then be used to raise (deactivate) the entire sun protection for this façade.</p> | |

5.17. Logic

Using this parameter window up to 4 logical AND-functions and up to 4 logical OR-functions with up to 4 data inputs (objects) are activated. Since the result of the logic operation can be inverted, if required, an AND-function can be changed into a NAND-function and an OR-function into a NOR-function.



| Parameter | Settings |
|--|-------------------------|
| AND logic operation 1 (...4) | inactive; active |
| Using this parameter the corresponding AND logic operation is activated. | |
| OR-logic operation 1 (...4) | inactive; active |
| Using this parameter the corresponding OR logic operation is activated. | |

0701 CO Weather station 910401

5.18. AND logic operation x, OR logic operation x

This parameter window is used to define for an AND / OR logic operation which object is assigned to an input, which actions should occur when the result of the logic operation is a logic 1 or a logic 0 and when or how the result should be transmitted on the bus.

AND logic operation 1

1st input:

2nd input:

3rd input:

4th input:

If logic operation = 1,

Action 1: Object value =

Action 2:

Scene number:

If logic operation = 0,

Action 1: Object value =

Action 2:

Scene number:

Send logic object:

| Parameter | Settings |
|--|--|
| 1st input (... 4th input) | not used; Object no. 6; ... Object no. 110 inverted |
| With this parameter an object of the weather station (from a list of approx. 40 objects) for logic combination with up to three further objects can be assigned to the corresponding input. | |
| If logic operation = 1 Action 1: Object value = | 0; 1 |
| If the result of the logic operation is = 1, if required it can be inverted via this parameter, i.e., an AND function then becomes a NAND function and an OR function a NOR function. | |
| Action 2: | not to be applied; recall 8-bit scene |
| If the result of the logic operation is = 1, as further action a selectable 8-bit scene can be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action 2" is set at "recall 8-bit scene". This parameter can be used to set the number of the desired scene in the range of 1...64. | |

| Parameter | Settings |
|---|--|
| If logic operation = 0, Action 1: Object value = | 0; 1 |
| If the result of the logic operation is = 0, if required it can be inverted via this parameter, i.e. an AND function then becomes a NAND function and an OR function becomes a NOR function. <i>Note:</i> If the parameter "If logic operation = 1, Action 1: Object value =" was set at "0", i.e., the result of the logic operation is inverted, it must be inverted here too and this parameter set at "1". | |
| Action 2: | not to be applied; recall 8-bit scene |
| If the result of the logic operation is = 0, as further action a selectable 8-bit scene can be recalled. | |
| Scene number | 1...64; 1 |
| This parameter is visible only when the previous parameter "Action 2" is set at "recall 8-bit scene." This parameter can be used to set the number of the desired scene in the range from 1...64. | |
| Send logic object | on change of value; on change of value and cyclically |
| This parameter is used to set when the result of the logic operation (i.e., the associated comm. object) should be sent on the bus. | |

GAMMA *instabus*

Application program description

April 2009

0701 CO Weather station 910401

Space for notices