Training Manual for Integrated Automation Solutions Totally Integrated Automation (TIA)

MODULE E11

Radio Frequency Identification (RFID)

with SIMATIC S7-300F-2 PN/DP and RF180C

This manual was prepared for training purposes by Siemens AG for the project *Siemens Automation Cooperates with Education* (SCE).

Siemens AG does not guarantee the contents of this document.

Passing on this document as well as copying it, using and communicating its contents is permitted within public training and continued education facilities. Exceptions require the written permission by Siemens AG (Michael Knust michael.knust@siemens.com).

Violators are held liable to pay damages. All rights -including translation- reserved, particularly if a patent is granted, or a utility model or design is registered.

We wish to thank the Michael Dziallas Engineering corporation and the instructors of vocational schools as well as all those who provided support during the preparation of this manual.

PAGE

1	PREFACE	5
2	Notes regarding the usage of CPU 315F-2 PN/DP	7
3	Notes regarding the SIMATIC RFID components	8
4	RFID Fundamentals	9
5	Starting up an RFID project with CPU 315F-2 PN/DP and RF180C	10
5.1	Setting Up a New Project	11
5.2	Configuring the Hardware	13
5.3	Assigning a Device Name	20
5.4	Inserting UDT Blocks and FB45	22
5.5	Generating Data Blocks	23
5.6	Programming a Restart or Warm Restart	33
5.7	FC11 Function for a Command or Request	34
5.8	Basics of Entries at Command Block FC11	36
5.9	Command String	39
5.10	Basics of FB45 and DB45	40
5.11	FB10 Reader_Control Program	51
5.12	FB1 Control Program	55
5.13	OB1 Program Call	61
5.14	Variable Table STATUS_SLG_1	62
5.15	Variable Table STATUS_SLG_2	63
5.16	Symbol Table	64
5.17	Block Folder	65
5.18	DB49 Data View	65

The following symbols serve as a guide through this module:



1 PREFACE



Regarding its content, Module E11 is part of the instruction unit **'IT Communication with SIMATIC S7**'.



Objective

In Module E11, the reader will learn how networking and data exchange between PLCs and RFID components is set up.

As PLC, the CPU 315F-2 PN/DP and as Radio Frequency Identification (RFID), a SIMATIC RFID system is used. The RFID components consist of the interface module RF180C (ASM) with write/read device RF310R (Reader or SLG (write/read device)) and different mobile data systems such as RF340T, RF350T, RF360T or ISO Moby D MDS D124 (transponder or MDS). PROFINET is used for networking the PLC and the SIMATIC RF180C.

Module E11 shows in principle the procedure for the startup, based on a brief example.

Prerequisites

To successfully work through Module E11, the following knowledge is assumed:

- How to handle Windows
- Fundamentals of PLC programming with STEP7 (for example, Module A 'Startup' PLC Programming with STEP7).
- Fundamentals of network engineering (for example, Appendix V Basics of Network Engineering)

i

Hardware and Software Required

- 1 PC, operating system Windows XP Professional with SP2 or SP3/Vista 32 bit Ultimate and Business/Server 2003 SP2 with 600MHz (only XP)/1 GHz and 512MB (only XP)/1 GB RAM, free disk storage approx. 650 to 900 MB, MS Internet Explorer 6.0 and network card
- 2 Software STEP 7 V 5.4
- 3 PLC SIMATIC S7-300 with CPU 315F-2 PN/DP and at least one digital Input and output module Sample configuration:
 - Power supply: PS 307 2A
 - CPU: CPU 315F-2 PN/DP
 - Digital inputs: DI 16x24V DC
 - Digital outputs: DO 16x24V DC/0.5 A
- 4 SIMATIC RF180C IM (interface module) RF310R or RF340R SLG (write/read device) Different transponder MDSs (Mobile Data System) of the type: RF340T (8 KB) RF350T (32 KB) RF360T (64 KB) ISO Moby D MDS D124 (112 bytes)
- 5 Ethernet connection between PC, CPU 315F-2 PN/DP and RF180C



NOTES REGARDING THE USAGE OF CPU 315F-2 PN/DP



2

The CPU 315F-2 PN/DP is a CPU that is shipped with 2 integrated interfaces.

- The first interface is a combined MPI/PROFIBUS DP interface that can be used at the PROFIBUS DP as master or slave to connect distributed IO/field devices with very fast reaction time.

In addition, it is possible to program the CPU here by means of an MPI or PROFIBUS DP

- The second interface is an integrated PROFINET interface.
 This allows for using the CPU as PROFINET IO controller to operate distributed IO on PROFINET. The CPU can be programmed by means of this interface also!
- Moreover, it is possible to use fail-safe IO devices on both interfaces.



Notes:

- In module E11, the CPU 315F-2 PN/DP is used as the controller for the data exchange of a SIMATIC RFID system on the PROFINET.
- To run this CPU, a micro-memory card is required!
- The addresses of the input and output modules can be parameterized at this CPU.

3 NOTES REGARDING THE SIMATIC RFID COMPONENTS



The communication module RF180C is a module for operating RFID components at any controller by means of PROFINET IO.

At the RF180C, up to 2 readers (SLG = write/read device) can be operated in parallel. The user can start a command in parallel on two readers (FB 45 if operated on a SIMATIC S7) The tag data is accessed by means of addressing the tag physically.

In the SIMATIC S7, FB 45 is provided for this. FB 45 makes available to the S7user an interface that is easy to handle and is equipped with powerful commands (processing a complete tag with a single command; command chaining; S7 data structures by means of UDTs).



The RF180C is integrated into the hardware configuration by means of a GSDML file. Then, the RF180C can be configured by means of HWConfig of the SIMATIC Manager. The GSDML file is provided on the CD "RFID Systems".



Additional information is available in the operating instructions "RFID Systems Communication Module RF180C".

4 RFID FUNDAMENTALS



Radio Frequency Identification (**RFID**) makes it possible to automatically identify and localize objects and living beings, and thus considerably facilitates recording and storing data. The RFID system consists of the following: 1) a transponder that is located in the object or in the living being and identifies it, and 2) a reading device for reading out the transponder ID. The reading device includes a software (a micro-program) that controls the actual read process, and an RFID middleware with interfaces to other EDP systems and data bases.

As a rule, a read device generates an electro-magnetic high frequency field with a short range, preferably with induction coils. It is not only used to transmit data, but to also to supply the transponder with power. Only if larger ranges are to be obtained are active transponders used that have their own power supply. Usually, the frequency of 13.56 MHz is used (RF300, ISO). The reading device (reader) generates a high frequency electromagnetic alternating field that illuminates the aerial of the RFID transponder (RFID tag). As soon as the aerial coil enters the electro-magnetic field, an induction current is generated in it. This current is rectified, and with it, a capacitor is loaded as short time storage which, for the read process, provides for the power supply of the chip. For active tags, an installed battery takes care of the supply. The micro-chip thus activated in the RFID tag decodes the commands sent by the reader. This reader encodes and modulates the reply into the irradiated electro-magnetic field through field weakening in the contact-free short circuit, or in opposition reflection of the field that the reader transmitted. With this, the tag transmits its own unchangeable serial number, additional numbers of the marked object, or other data that the reader polled. The transponder itself does not transmit a field; it only changes the reader's electro-magnetic transmission field.



Readout

Station

Readout Station

Transponder switch closed, aerial is on "Reflect", (return value 1). (Source: Wikipedia)

5

STARTING UP AN RFID PROJECT WITH CPU 315F-2 PN/DP AND RF180C

Below, the startup of an RFID project is described. As SIMATIC S7-300 station, the CPU 315F-2 PN/DP is used.

In the CPU's control program, a data structure has to be generated -by means of a function block call (FB45)- with data blocks and embedded UDT data types.

In our example, it has to be possible to perform the following actions for each reader:

- Writing data to the transponder (DB48 of the CPU to the MDS).
- Reading the data from the transponder (MDS to DB48 of the CPU).
- Reading the transponder data information (MDS to DB49 of the CPU).
- Reading the reader status information (reader to DB50 of CPU).

The data structure of the German language UDTs is as follows:



To generate the data structure, the required UDT data types have to be imported to the Step 7 project and function block FB45.

A sample program with the blocks is provided on the CD "RFID Systems".



Additional information about the data structure is available in the function manual "RFID Systems FB45"

5.1 Setting Up a New Project



The central tool in STEP 7 is the 'SIMATIC Manager', which we call here with a double click. (
→ SIMATIC Manager)



2. STEP 7 programs are managed in projects. We are now setting up such a project $(\rightarrow File \rightarrow New)$

SIMATIC Manager		_1
atei Zielsystem Ansicht Extras Fenster Hilfe		
Neu	Strl+N	
Assistent 'Neues Projekt' Öffnen	Ctrl+O	
57-Memory Card Memory Card-Datei		
Löschen Reorganisieren Verwalten		
Archivieren Dearchivieren		
Seite einrichten		
1 PROFIsafe02 (Projekt) F:\0_57_Projekte\PROFIs_2 2 Profi Umrichter (Projekt) F:\0_57_Projekte\Profi_Um 3 Erreichbare Teilnehmer PROFIBUS		
Beenden	Alt+F4	

3. Next, we are assigning the '**Name**' '**RFID_RF180C**' to the project (\rightarrow RFID_RF180C \rightarrow OK)





- 4. Highlight your project and insert an 'Industrial Ethernet Subnet'
 - $(\rightarrow \text{RFID}_\text{RF180C} \rightarrow \text{Insert} \rightarrow \text{Subnet} \rightarrow \text{Industrial Ethernet}).$



5. Then, we insert a 'SIMATIC 300 Station'. (\rightarrow Insert \rightarrow Station \rightarrow SIMATIC 300 Station)



5.2 Configuring the Hardware



6. With a double click, open the configuration tool for the **'Hardware'**. (\rightarrow Hardware)



7. Open the hardware catalog by clicking on the symbol 1. $(\rightarrow \textcircled{1})$ Insert the '**Mounting channel**' with a double click (\rightarrow SIMATIC 300 \rightarrow RACK 300 \rightarrow Mounting channel).





Note

A configuration table for configuring Rack 0 is displayed automatically.

TIA Training Document Module E11 Status: 01/2010 RF180C Page 13 of 65



8. From the hardware catalog, we can now select all modules that are present in the actual rack and insert them in the configuration table. To this end, we click on the name of the respective module, hold the mouse key and drag it to a line in the configuration table.

We start with the power unit '**PS 307 5A**' (\rightarrow SIMATIC 300 \rightarrow PS-300 \rightarrow PS 307 5A).

HW Konfig	- [SIMATIC 300(* arbeiten Einfügen	1) (Konfigur a Zielsystem Ar	ation) R Isicht Extra	FID_RF1	BOC] Hilfe		_	_	_		-	
0 🚅 🔓 🖩	1 F1 B B	C. 🔬 🎪		₩ №?								
							_	_	^			
	PS 307 54	1								Suchen:		mt mi
2	1.0.007.08									<u>P</u> rofil:	Standard	•
4 5 6 7 7 8 9 10 11 11 € € 0	ur,								×		PROFIBUS-DP PROFIBUS-PA PROFINET 10 SIMATIC 300 C7 CP-300 CPU-300 IM-300 M-72EXTENSION Netzübergang PS-300 PS-300 PS-300 PS-300 PS-307 10A	
Steckplatz	Baugruppe	Best	ellnummer	0440	Firmware	MPI-Adresse	E	A	K		PS 307 10A	
2		0231	301-1EA00	0000							PS 307 5A	
3						5				±-(SM-300	
5						5				÷ 🔛	SIMATIC 400 SIMATIC HMI Station	
$\frac{6}{7}$									_	±	SIMATIC PC Based Control (300/400
8						5				÷ 👱	SIMATIC PC Station	
9 10							-			6ES7 30	17-1F400-0440	
11		105				5				Laststroi AC:24VI	nversorgung 120/230V DC/5A	
Einfügen möglich									-	H		Änd



Note

If your hardware deviates from the one displayed here, simply select the corresponding modules from the catalog and insert them in your rack. The order numbers for the individual modules -that are also inscribed on the modules- are displayed in the footer of the catalog.



9. Next, we drag the 'CPU 315F-2 PN/DP' to the second slot.

The order number and the version of the CPU are inscribed on the front of the CPU. (\rightarrow SIMATIC 300 \rightarrow CPU-300 \rightarrow CPU 315F-2 PN/DP \rightarrow 6ES7 315-2FH13-0AB0 \rightarrow V2.6)

	earbeiten Einfügen Zielsy:	stem Ansicht Extras Fenster	Hilfe							- 8
) 🚅 🔓	• • • • • • • • • • • • • • • • • • •	🕯 🏟 📳 🗖 🚼 🕅								
							^			
1	Π PS 307 5Δ							Suchen:	[m† 0
2								<u>P</u> rofil:	Standard	
3 4 5 6 7 8 9 10 11							>		CPU-300 CPU-312 CPU-312 IFM CPU-312 IFM CPU-313 CPU-313C CPU-313C-2 DP CPU-313C-2 DP CPU-314C-2 DP CPU-314 IFM CPU-314C-2 DP CPU-314C-2 PtP CPU-315	
iteckplatz	Baugruppe	Bestellnummer	Firmware	MPI-Adresse	E	A	К	1	E D CPU 315-2 DP E D CPU 315-2 PN/D	P
	PS 307 34	6ES7 307-TEAUU-UAAU		1				{	CPU 315F-2 DP CPU 315F-2 DP	0.0
	-			-			_		E CPU 315F-2 PN/	H10-0ABC
; ;			0	0 0			=		😑 🦲 6ES7 315-2FI	H13-QABC
			6	5					- V2.5	Ó
;		4							-	
3 7 3 3				0	2		-	<	111	>

10. When entering the CPU, the following window appears. In this window, we do the following: assign to CPU 315F-2 PN/DP an 'IP- address', specify the 'Subnet screen form' and select the 'Ethernet' that has already been set up. Optionally, a 'Router address' can be selected for network-overarching communication. Confirm your entries with 'OK' (→ IP address: 192.168.0.100 → subnet screen form: 255.255.255.0 → Ethernet(1) → Don't use a router → OK)

IP-Adresse: 192.168.0.100 Subnetzmaske: 255.255.255.0		Netzübergang Keinen Router vo Router verwende Adresse: 192	erwenden en 168.0.100
Subnetz: nicht vernetz	t:		Neu
Ethernet[1]			Eigenschaften



Notes regarding networking on the Ethernet (additional information is provided in Appendix V of the training manual):

MAC address:

The MAC address consists of a permanent and a variable part. The permanent part ("Basic MAC address") identifies the manufacturer (Siemens, 3COM, ...). The variable part of the MAC address differentiates the different Ethernet stations and should be assigned globally unique. On each module, a MAC address specified by the factory is inscribed.

Value range for the IP address:

The IP address consists of 4 decimal numbers in the value range 0 to 255, separated by a period; for example: 141.80.0.16

Value range for the subnet screen form:

This screen form is used to establish whether a station or its IP address belongs to the local subnet, or can be reached only by means of a router.

The subnet screen form consists of 4 decimal numbers in the value range 0 to 255, separated by a period; for example: 255.255.0.0

The 4 decimal numbers of the subnet screen form have to contain -in their binary representationfrom the left a series of gapless values "1" and from the right a series of gapless values "0".. The values "1" determine the area of the IP address for the network number. The values "0" determine the area of the IP address for the station address.

Example:

 Correct values:
 255.255.0.0 Decimal = 1111 1111.1111 1111.0000 0000.0000 0000 binary

 255.255.128.0 Decimal = 1111 1111.1111 1111.0000 0000.0000 0000 binary

 255.254.0.0 Decimal = 1111 1111.1111 1110.0000 0000.0000 binary

 Incorrect value:
 255.255.1.0 Decimal = 1111 1111.1111 1111.0000 0000.0000 binary

Value range for the address of the gateway (router):

The address consists of 4 decimal numbers in the value range 0 to 255 separated by a period; for example, 141.80.0.1.

Relationship of the IP addresses, router address and subnet screen form:

The IP address and the gateway address must differ only at those positions where an "0" is shown in the subnet screen form.

Example:

You entered the following: for subnet screen form 255.255.255.0; for IP address 141.30.0.5 and for router address 141.30.128.1.

The value for the IP address and the gateway address is to differ only in the 4th decimal number. However, in the example, the 3rd position already differs.

In the example, we have to alternatively change:

- the subnet screen form to: 255.255.0.0 or
- the IP address to: 141.30.128.5 or
- the gateway address to: 141.30.0.1



11. Next, we are dragging the input module for 16 inputs to the 4th slot. The module's order number is located on the front. (→ SIMATIC 300 → DI-300 → SM 321 DI16x24VDC).





Note

Slot 3 is reserved for interface modules and remains empty for that reason. The module's order number is indicated in the footer of the catalog.



12. Now we drag the output module for 16 outputs to the 5th slot. The module's order number is located on the front (\rightarrow SIMATIC-300 \rightarrow DO-300 \rightarrow SM 322 DO16x24VDC/0.5A).

	HW Konf	ig - [SIMATIC 300(1) (Kon	figuration) RFID_RF18	0C]								. 🗆 🛛
Ш비	Station B	Bearbeiten Einfügen Zielsyste	em Ansicht Extras Fenster	Hilfe								×
) 🖨 🔓	• • • • • • • • • • • • • • • • • • •	â â 🗊 🗖 🔡 🕅									
	Ethernet((1): PROFINET-IO-System (100)						~				
	20 00 U	IR							Suchen:	1		mtmi
	1	📔 PS 307 5A 🛛 🔼							200000	76		
	2	CPU 315F-2 P							Profil:	Standard		-
	XI	MPI/DP							1		200	-
-	- X2	PN-IO									-300 SM 322 DD16v	AC120
	$\frac{\chi_2 p_1}{2}$	Port 7									SM 322 D016x	AC1200
	3										SM 322 D016x	AC120v
	5										SM 322 D016x	DC24V/
	6	1 DOTONO CENTRO								🚺	SM 322 D016x	DC24V/
	7									1 8-0	SM 322 D016x	DC24V/
	8	~								 	SM 322 D016x	DC24V
		and a second a second a						~		1	SM 322 D016x	DC24V
<		- MIC						>			SM 322 D016x	DC24V/
											SM 322 D016x	Rel.AC ⊒
4	= > (0)) UR									SM 322 DU16x	HELAL
-		Long		1	E	2					SM 322 DU16X	002474 AC120.:
9	Steckplatz	Baugruppe	Bestellnummer	Firmware	MPI-Adresse	E	A	K			SM 322 D032x	AC1204
		PS 307 5A	6ES7 307-1EA00-0AA0					^			SM 322 DD32x	DC24V
	2	CPU 315F-2 PN/DP	6ES7 315-2FH13-UABU	¥2.6	2	2047		-			SM 322 DO4xD	C15V/2
	87 Wa	NFS/DF	-		2	20141		-			SM 322 DO4xD	C24V/1
	42 V2 D1	Fivill East 1		-		2040		-			SM 322 D064x	DC24V/
	3277	1 1 1011				2040	0.0				SM 322 D064x	DC24V/
	1	DI16xDC24V	6ES7 321-18H01-0440			0 1		-			SM 322 D08xA	C Iso
E	5	D016xDC24V/0.5A	6ES7 322-1BH01-0AA0				45	-			SM 322 D08xA	C120/2 🗸
E	3								4	.uu		>
17	7								6ES7 32	2-1BH01-0	IAA0	A Er
8	3								Digitalau	isgabebaug	gr. D016	1-1
9	3			1				v	SIPLUS.	A, Wurzelu Baugruppe	ng 8; auch als mit	
Ľ		15								e angroppe		M
Einfü	iaen möalic	th .										And /



Note

The module's order number is indicated in the footer of the catalog.

13. Now, we have to change the PROFINET device name to PN IOx100. Select '**PN-IO**' with a double click. (\rightarrow PN-IO, \rightarrow PN-IOx100, \rightarrow OK)

Eigenschaften - PN	-10 (R0/S2.2)				
Allgemein Adressen	PROFINET S	ynchronisation Uhrze	eitsynchronisati	on	
Kurzbezeichnung:	PN-IO				
Gerätename:	PN-I0x100				
Schnittstelle	Ethernet				
Gerätenummer:	0				
Adresse:	192.168.0.100				
Vernetzt:	ja	Eigenschaften			
Kommentar:					
1					
OK				Abbrechen	Hilfe



14. Now, drag the PROFINET IO System (100) module tier toward the right and from the folder PROFINET IO, insert the SIMATIC RFID module RF180C into the module tier by dragging it there.

If module RF180C should not yet be selectable, it first has to be inserted by a data carrier, using the menu "Options" Install GSD files.



15. Then, double click on the inserted module and change the device name to RF180Cx110 and the IP address to 192.168.0.110

Allgemein 10-Zyklus				
Kurzbezeichnung:	RF180C			
	Kommunikationsmodul RF18 PROFINET 10	30C (IP67) zur Verbindung zwe	ier Reader mit	2
Bestell-Nr. / Firmware:	6GT2 002-0JD00			
Familie:	SIMATIC RFID			
Gerätename:	RF180Cx110			_
GSD-Datei:	GSDML-V1.0-SIEMENS-RF Ausgabestand ändem	180C-20070122.xml		
GSD-Datei:	GSDML-V1.0-SIEMENS-RF Ausgabestand andem	180C-20070122.xml		
GSD-Datei: Teilnehmer PROFINE Gerätenummer:	GSDML-V1.0-SIEMENS-RF Ausgabestand ändern	180C-20070122.xml)	
GSD-Datei: Teilnehmer PROFINE Gerätenummer: IP-Adresse:	GSDML-V1.0-SIEMENS-RF Ausgabestand ändern T IO-System 192.168.0.110	180C-20070122.xml PR0FINET-IO-System (100)	
GSD-Datei: Teilnehmer PROFINE Gerätenummer: IP-Adresse; IP-Adresse durch	GSDML-V1.0-SIEMENS-RF Ausgabestand ändern T IO-System 132.168.0.110 IO-Controller zuweisen	180C-20070122.xml PROFINET-IO-System (100Ethernet)	
GSD-Datei: Teilnehmer PROFINE Gerätenummer: IP:Adresse: IP:Adresse durch Kommentar:	GSDML-V1.0-SIEMENS-RF Ausgabestand ändern T IO-System 192.168.0.110 IO-Controller.zuweisen	180C-20070122.xml PROFINET-IO-System (100 Ethernet	1	
GSD-Datei: Teilnehmer PROFINE Gerätenummer: IP-Adresse: IP-Adresse durch Kommentar:	GSDML-V1.0-SIEMENS-RF Ausgabestand ändern 1 IO-System 1 22.168.0.110 IO-Controller.guweisen	180C-20070122.xml PROFINET-IO-System (100 Ethernet)	
GSD-Datei: Teilnehmer PROFINE Gerätenummer: IP-Adresse: IP-Adresse durch Kommentar:	GSDML-V1.0-SIEMENS-RF Ausgabestand ändern 1 IO-System 1 22.168.0.110 IO-Controller.zuweisen	190C-20070122.xml PROFINET-IO-System (100 Ethernet)	0

16. By clicking on ',, the hardware configuration is saved and compiled.

5.3 Assigning a Device Name



17. First, highlight the module RF180C and then select, under the menu "Destination system" and under Ethernet **Assign device name**.

Dig HW	/ Konfig - [SIMATIC 300(1) (Konfi	guration) RFI	D_RF180C]						
	🗧 🔓 🗣 🗣 🎼 🎒 🗎 🗈	Laden ir	Baugruppe	Penster H	Ctrl+L						
2 [⇒(0) UR 1 I PS 307 5A 4	Baugrup	open-Identifikation la open-Identifikation la	aden aden in PG		00)		< III	S <u>u</u> chen:		- □× n† ni
	2 I CPU 315F-2 P X1 MP//DP X2 P//Ox100 X2P1 Pont 1 3	Gestört Baugrup Betriebs Urlösch Uhrzeit Beobac	e Baugruppen ppenzustand szustand en stellen hter/Steuern		Ctrl+D Ctrl+I					Standard PROFIBUS-DP PROFIBUS-PA PROFINET IO Drives Gateway	
<	6 7 8 ()	Firmwar Geräter Etherne	re aktualisieren namen auf Memory C It	ard speicher	n	Ethernet-Te	ilnehmer	↓ bearbeite	m	I/O Ident Systems Ident SIMATIC RFID Ing SIMATIC RFID	
-	→ (1) RF180Cx110	PROFIB	US			Gerätename Gerätename	n überpr n vergeb	üfen ien		Sensors	
Stee	kplatz Baugruppe	Reader	Bestellnummer		E-Adresse	A-Adresse	Diag 2043*	К		SIMATIC 300 SIMATIC 400 SIMATIC HMI Station	
						,			GGT2 00 SIEMEN Kommur	SIMATIC PC Based Control 30 SIMATIC PC Station 12-0JD00 IS ikationsmodul RF180C (IP67)	0/400
Vernabe	von PROFINET TO Device-Ger	ätenamen							Junivero	indong zweier medder fillt	≚ Ănd



Note

A prerequisite for this is that the die PG/PC interface is set to TCP/IP and the PC's network card is configured correctly. For example, IP address 192.168.0.99, subnet 255.255.255.0 and router address -.-.- (refer to Module E02)

18. Highlight the SIMATIC RFID module and then click on the button "Assign name". Then close the window.

eratename:	RF180Cx110	💌 Gerà	itetyp: SIMATIC RF	ID
orhandene Ger IP-Adresse	äte: MAC-Adresse	Gerätetvo	Gerätename	Name zuweisen
192.168.0.110	08-00-06-99-28-BA	SIMATIC RFID	RF180Cx110	Teilnehmer-Blinktest Dauer (Sekunden): 3
nur Geräte d	leichen Typs anzeige	n 🔲 nur Geräte	ohne Namen anzeige	en



This is what the completed hardware configuration with the associated addresses looks like

19. By clicking on ' $\overset{()}{\underline{m}}$ ' we can load the hardware configuration to the PLC. The operating mode switch on the CPU should be on Stop (\rightarrow).



dressen v	von:		٨d	resshereich von:	0	bie:	2047		
CPU 315	F-2 PN/DP		Au	iessbereicht voh.		Dis.	2041		
			Fre	ee Adressvergabe:	Ja				
			Ba Ste	ugruppenträger/ eckplatz:	0/2	CPU-	Nr: 1		
ilter: 🔽	Eingänge	🔽 Ausg	änge 🔽 Adresslück	en					
Тур	Adr. von	Adr. bis	Baugruppe	TPA	DP	PN	B	S	IF
E	0	1	DI16xDC24V	OB1-PA	-	-	0	4	-
Ē	2	255	Lücke	•	-	-	•	•	-
E	256	259	Anschluss zweier Reade	r OB1-PA	12	100(1)	12	1	0
E	260	2042	Lücke		24		82 C	1	-
E*	2043	2043	RF180Cx110	.e	18	100(1)	88.	0	0
E×	2044	2044	PN-IOx100	15	10		0	2	2
Ε×	2045	2045	Port 1	12	12	20	0	2	3
E×	2046	2046	PN-I0x100	Q2	34 2	94), 1	0	2	2
E*	2047	2047	MPI/DP	(e)	58	83	0	2	1
4	0	3	Lücke	15	1	52	15	5. .	13
А.	4	5	D016xDC24V/0.5A	OB1-PA	12	20	0	5	177
4	6	255	Lücke	unerena di	26		<u> </u>	-	11
Δ.	256	259	Anschluss zweier Reade	r OB1-PA	58	100(1)	98	1	0
	000	2047	1 Gebe			103203		10000	-

20. Close hardware configuration.

5.4 Inserting UDT Blocks and FB45



De-archive the library "**RFID_FB45_UDT_Blocks**" from the template directory and open it. Copy **UDT11**, **UDT21**, **UDT 111**, **UDT261**, **UDT271**, **UDT281** and **FB45** and insert them in the block folder.

Close the library.

BFID_RF180C	Systemdaten	OB1 ODT111	FB45	UDT11
CPU 315F-2 PN/DP ST-Programm(2) Duellen CPU Bausteine	UDT281	G round	() () ()	G 001211
RFID_FB45_UDT_Baustein	ne C:\Program	n Files\Siemens\St	ep7\S7libs\RFID_f	B4
HFID_FB45_UD1_Bausteine				
Cuellen				
Bausteine				
		GUDT111		LIDT120
	LIDT121	LIDT124	LIDT130	G UDT131
	UDT134	LUDT140	DDT141	UDT144
		UDT261	DT264	UDT270
	1 UD1260			Contraction of the second second
	UDT271	DT274	UDT280	🔲 UDT281



Note

Instead of the library **RFID_FB45_UDT_Blocks**, the sample program MOBY FB45 can be dearchived. The file **FB45_V1_3.zip** is available on the RFID Systems CD in the directory "Data", subdirectory "FB45".

RFID_RF180C C:\Program Files\Siemens\Step7\s7proj\RFID_R_5							
BRID_RF180C SIMATIC 300(1) G CPU 315F-2 PN/DP S7-Programm(2) Quellen Bausteine	Systemdaten UDT21 UDT281	⊕ 0B1 ⊕ UDT111	₽ FB45 ₽ UDT261	G UDT11 G UDT271			
B MOBY FB45 C:\Program	Files\Siemens\S	tep7\\$7Proj\FB45_V	1_3				
🖃 🎒 MOBY FB45	🕞 0B1	🖪 OB80	🔁 0882	🔁 0B86			
🖻 🛐 FB45	🔁 OB100	🖪 OB121	🔁 OB122	🗗 FB 45			
Quellen	🔁 DB11	🖪 DB12	🖽 DB45	🖽 DB47			
Bausteine	🕞 DB48	🖽 DB60	🖽 DB61	🖽 DB62			
	🖪 DB63	🖽 DB64	🕞 DB73	🖪 DB74			
	🔁 DB75	🖽 UDT10	🖽 UDT11	🖽 UDT14			
	UDT20	🔲 UDT21	🖽 UDT24	🖽 UDT60			
	DDT61	🖽 UDT64	🖽 UDT70	🖽 UDT71			
	UDT74	🔁 UDT100	🔁 UDT101	🕞 UDT104			
	🔁 UDT110	🔁 UDT111	🖽 UDT114	🔁 UDT120			
	🔁 UDT121	🖪 UDT124	🕞 UDT130	🖪 UDT131			
	🔁 UDT134	🖽 UDT140	🖽 UDT141	🕞 UDT144			
	🔁 UDT260	🖪 UDT261	🖽 UDT264	🗗 UDT270			
	🔁 UDT271	🗊 UDT274	🖽 UDT280	UDT281			
	DT284	Market Status Channel 1	Manual 2 Status Channel 2	0452			

5.5 Generating Data Blocks



DB48 Write/Read Data

Here, the source data of a write request to the transponder is stored, or the destination data for the read request from the transponder.

Generating DB48

Eigenschaften - Datenl	paustein			×		
Allgemein - Teil 1 Allgeme	in • Teil 2 Aufrufe	Attribute				
Name und Typ:	DB48	Global-DB	•	×		
Symbolischer Name:	S_L_DATEN					
Symbolkommentar:	hier werden die Date	en des Schreib	Lese Auftrags eingetrag	gen		
Erstellsprache:	DB					
Projektpfad:	[
Speicherort des Projekts:	C:\Program Files\Siemens\Step7\s7proj\RFID_R_5					
Erstellt am:	Code 06.12.2009 08:47:43		Schnittstelle			
Zuletzt geändert am:	06.12.2009 08:47:43		06.12.2009 08:47:43			
Kommentar:				~		
				1		
				<u>×</u>		
ОК			Abbrechen	Hilfe		

Open DB48, set up 1024 bytes

Under Name, enter "Data". At Type Combined data, select (with the right mouse key) the ARRAY data format. Enter **1..1024** within the brackets. In the next line, select or enter BYTE.

🎼 KOP/AW	L/FUP - [DB48 "S_L_DATEN	" RFID_RF180C\SIMATIC 3	00(1)\CPU 315F-	2 PN/DP\\DB48]
🖬 Datei Be	arbeiten Einfügen Zielsystem Tes	t Ansicht Extras Fenster Hilfe		
🗅 🚔 🔓		0% 🏙 🔽 😤 6° !«>!		
Adresse	Name	Тур	Anfangswert	Kommentar
*0.0		STRUCT		
+0.0	Daten	ARRAY[11024]		
*1.0		BYTE		
=1024.0		END_STRUCT		

Save and close DB48





DB49 MDS Status Information

In DB49, the MDS status Information is entered. The information is stored in a data block with a specified structure. Read MDS status with Sub_Command 01according to UDT261 or Sub_Command 02 according to UDT271.

Generating DB49

Eigenschaften - Datenl	paustein						
Allgemein - Teil 1 Allgeme	ein - Teil 2 Aufrufe	Attribute					
Name und Typ:	DB49	Global-DB	•	Ŧ			
Symbolischer Name:	MDS_STATUS						
Symbolkommentar:	hier werden die MDS	S-Status Inform	nationen abgelegt				
Erstellsprache:	DB						
Projektpfad:	1						
Speicherort des Projekts:	ekts: C:\Program Files\Siemens\Step7\s7proj\RFID_R_5						
e	Code		Schnittstelle				
Erstellt am: Zuletzt geändert am:	06.12.2009 09:09:26		06.12.2009 09:09:26	s			
Kommentar:	-			~			
	1			~			
ОК			Abbrechen	Hilfe			

Open DB49 and insert UDT261 and UDT271

Adresse	Name	Тур	Anfangswert	Kommentar
0.0		STRUCT		
+0.0	MDS_Status0	"MOBY P MDS-Status 0_d"		hier ist der UDT261 abgelegt
+18.0	MDS_Status1	"MOBY P MDS-Status 1_d"		hier ist der UDT271 abgelegt
=36.0		END_STRUCT		

DB49 data view

Adresse	Name	Typ	Anfangswert	Aktualwert	Kommentar
0.0	MDS_Status0.reserved0	BYTE	B#16#0	B#16#0	
1.0	MDS_Status0.status_info	BYTE	B#16#0	B#16#0	Modus MDS-Status
2.0	MDS_Status0.UID[1].Byte_1_4	DWORD	DW#16#0	DW#16#0	MDS-Nummer (unique identifier)
6.0	MDS_Status0.UID[1].Byte_5_8	DWORD	DW#16#0	DW#16#0	
10.0	MDS_Status0.MDS_type	BYTE	B#16#0	B#16#0	MDS-Typ
11.0	MDS_Status0.Lock_state	BYTE	B#16#0	B#16#0	Schreibschutzstatus BEPROM
12.0	MDS_Status0.reserved1[1]	BYTE	B#16#0	B#16#0	
13.0	MDS_Status0.reserved1[2]	BYTE	B#16#0	B#16#0	
14.0	MDS_Status0.reserved1[3]	BYTE	B#16#0	B#16#0	
15.0	MDS_Status0.reserved1[4]	BYTE	B#16#0	B#16#0	
16.0	MDS_Status0.reserved1[5]	BYTE	B#16#0	B#16#0	
17.0	MDS_Status0.reserved1[6]	BYTE	B#16#0	B#16#0	
18.0	MDS_Statusl.reserved0	BYTE	B#16#0	B#16#0	
19.0	MDS_Statusl.status_info	BYTE	B#16#0	B#16#0	Modus MDS-Status
20.0	MDS_Status1.UID[1].Byte_1_4	DWORD	DW#16#0	DW#16#0	MDS-Nummer (unique identifier)
24.0	MDS_Status1.UID[1].Byte_5_8	DWORD	DW#16#0	DW#16#0	
28.0	MDS_Status1.LFD	BYTE	B#16#0	B#16#0	Leistungsflussdichte: Beziehung zwischen Grenzwert und gemessenem Wert
29.0	MDS_Status1.FZP	BYTE	B#16#0	B#16#0	Fehlerzähler passiv (Ruhefehlerzähler)
30.0	MDS_Status1.FZA	BYTE	B#16#0	B#16#0	Fehlerzähler aktiv (Fehler während Kommunikation)
31.0	MDS_Status1.ANWZ	BYTE	B#16#0	B#16#0	Anwesenheitszähler
32.0	MDS_Status1.reserved1[1]	BYTE	B#16#0	B#16#0	
33.0	MDS_Status1.reserved1[2]	BYTE	B#16#0	B#16#0	
34.0	MDS_Status1.reserved1[3]	BYTE	B#16#0	B#16#0	

The start address in DB49 is "0" for Sub_Command 01 and "18" for Sub_Command 02. The data length is 18 bytes in both cases



Save and close DB49





DB50 Reader Status Information

The reader status information is entered in DB50.

Depending on the request, the information has to be stored in a data block with a specified data structure.

Read reader status with Sub_Command 01 according to UDT111 or Sub_Command 06 according to UDT281.

Generating DB50

Eigenschaften - Datenl	baustein			
Allgemein - Teil 1 Allgeme	ein - Teil 2 Aufrufe	Attribute		
Name und Typ:	DB50	Global-DB	•	*
Symbolischer Name:	SLG_STATUS			
Symbolkommentar:	hier werden die SLG	-Status Informa	ationen abgelegt	
Erstellsprache:	DB			
Projektpfad:				
Speicherort des Projekts:	C:\Program Files\Si	emens\Step7\s	s7proj\RFID_R_5	
_	Code		Schnittstelle	
Erstellt am: Zuletzt geändert am:	06.12.2009 12:18:52 06.12.2009 12:18:52	-	06.12.2009 12:18:52	2
Kommentar:				1
ОК	,		Abbrechen	Hilfe

Open DB50 and insert UDT111 and UDT281

Open DB50 and insert UDT111 for Reader_Status. For Reader_diagnosis, insert UDT281.

Adresse	Name	Тур	Anfangswert	Kommentar
0.0		STRUCT		
+0.0	SLG_Status	"MOBY SLG-Status_d"		hier ist der UDT111 abgelegt
+28.0	SLG_Diagnose	"MOBY P SLG-Status_d"		hier ist der UDT281 abgelegt
=56.0		END_STRUCT		



Data view of the Reader status in DB50 (UDT111) Byte 0 to 27

Adresse	Name	Typ	Anfangswert	Aktualwert	Kommentar
0.0	SLG_Status.status_info	BYTE	B#16#0	B#16#0	Modus SLG-Status
1.0	SLG_Status.hardware	CHAR	1.0	1.1	HW-Variante
2.0	SLG_Status.hardware_version	WORD	W#16#0	W#16#0	HW-Version
4.0	SLG_Status.loader_version	WORD	W#16#0	W#16#0	Urlader-Version
6.0	SLG_Status.firmware	CHAR	1.12		FW-Variante
8.0	SLG_Status.firmware_version	WORD	W#16#0	W#16#0	FW-Version
10.0	SLG_Status.driver	CHAR	1000		Treiber-Variante
12.0	SLG_Status.driver_version	WORD	W#16#0	W#16#0	Treiber-Version
14.0	SLG_Status.interface	BYTE	B#16#0	B#16#0	Schnittstelle (RS 232 / RS 422)
15.0	SLG_Status.baud	BYTE	B#16#0	B#16#0	Baudrate
16.0	SLG_Status.reserved1	BYTE	B#16#0	B#16#0	Reserviert
17.0	SLG_Status.reserved2	BYTE	B#16#0	B#16#0	Reserviert
18.0	SLG_Status.reserved3	BYTE	B#16#0	B#16#0	Reserviert
19.0	SLG_Status.distance_limiting_SLG	BYTE	B#16#0	B#16#0	Reichweitenbegrenzung
20.0	SLG_Status.multitag_SLG	BYTE	B#16#0	B#16#0	Multitag SLG
21.0	SLG_Status.field_ON_control_SLG	BYTE	B#16#0	B#16#0	Berobetriebsart
22.0	SLG_Status.field_ON_time_SLG	BYTE	B#16#0	B#16#0	Berozeit
23.0	SLG_Status.sync_SLG	BYTE	B#16#0	B#16#0	Semaphorensteuerung (Synchronisation mit SLG)
24.0	SLG_Status.status_ant	BYTE	B#16#0	B#16#0	Status Antenne
25.0	SLG_Status.stand_by	BYTE	B#16#0	B#16#0	Standby Zeit nachdem ein Befehl ausgeführt wurde
26.0	SLG_Status.MDS_control	BYTE	B#16#0	B#16#0	Anwesenheit

Data view of the Reader diagnosis in DB50 (UDT281) Byte 28 to 55

28.0 SLG_Diagnose.status_info	BYTE	B#16#0	B#16#0	Modus SLG-Status
29.0 SLC_Diagnose.FZP	BYTE	B#16#0	B#16#0	Fehlerzähler passiv (Ruhefehlerzähler)
30.0 SLG_Diagnose.ABZ	BYTE	B#16#0	B#16#0	Abbruchzähler
31.0 SLG_Diagnose.CFZ	BYTE	B#16#0	B#16#0	Codefehlerzähler
32.0 SLC_Diagnose.SFZ	BYTE	B#16#0	B#16#0	Signaturfehlerzähler
33.0 SLG_Diagnose.CRCFZ	BYTE	B#16#0	B#16#0	CRC-Fehlerzähler
34.0 SLG_Diagnose.BSTAT	BYTE	B#16#0	B#16#0	Befehlsstatus
35.0 SLG_Diagnose.ASMFZ	BYTE	B#16#0	B#16#0	Fehlerzähler Hostinterface (ASM)
36.0 SLG_Diagnose.reserved0[1]	BYTE	B#16#0	B#16#0	
37.0 SLG_Diagnose.reserved0[2]	BYTE	B#16#0	B#16#0	
38.0 SLC_Diagnose.reserved0[3]	BYTE	B#16#0	B#16#0	
39.0 SLG_Diagnose.reserved0[4]	BYTE	B#16#0	B#16#0	
40.0 SLG_Diagnose.reserved0[5]	BYTE	B#16#0	B#16#0	
41.0 SLG_Diagnose.reserved0[6]	BYTE	B#16#0	B#16#0	
42.0 SLG_Diagnose.reserved0[7]	BYTE	B#16#0	B#16#0	
43.0 SLC_Diagnose.reserved0[8]	BYTE	B#16#0	B#16#0	
44.0 SLG_Diagnose.reserved0[9]	BYTE	B#16#0	B#16#0	
45.0 SLG_Diagnose.reserved0[10]	BYTE	B#16#0	B#16#0	
46.0 SLG_Diagnose.reserved0[11]	BYTE	B#16#0	B#16#0	
47.0 SLG_Diagnose.reserved0[12]	BYTE	B#16#0	B#16#0	
48.0 SLG_Diagnose.reserved0[13]	BYTE	B#16#0	B#16#0	
49.0 SLG_Diagnose.reserved0[14]	BYTE	B#16#0	B#16#0	
50.0 SLG_Diagnose.reserved0[15]	BYTE	B#16#0	B#16#0	
51.0 SLG_Diagnose.reserved0[16]	BYTE	B#16#0	B#16#0	
52.0 SLG_Diagnose.reserved0[17]	BYTE	B#16#0	B#16#0	
53.0 SLC_Diagnose.reserved0[18]	BYTE	B#16#0	B#16#0	
54.0 SLG_Diagnose.reserved0[19]	BYTE	B#16#0	B#16#0	
55.0 SLG Diagnose.reserved0[20]	BYTE	B#16#0	B#16#0	

For Sub_Command 01, the start address in DB50 is "0" Reader status information and for Sub_Command 06 "28" Reader diagnosis information. The data length in both cases is 28 bytes.

Save and close DB50



DB47 Request Data Block

The DB47 is set by means of the UDT11 in DB45. In DB47, a UDT21 is embedded for each reader. The request commands are then entered in the respective UDT21. The data of the read/write request is then stored in DB48. The reference to DB48 is assigned in UDT21 of DB47.

Generate DB47

Eigenschaften - Datenl	baustein			×
Allgemein - Teil 1 Allgeme	ein - Teil 2 Aufrufe	Attribute		
Name und Typ: Symbolischer Name:	DB47 AUFTRAG	Global-DB	•	*
Symbolkommentar:	hier werden die Kom	mandos einge	egeben	
Erstellsprache:	DB			
Projektpfad:				
Speicherort des Projekts:	C:\Program Files\Sie	mens\Step7	\s7proj\RFID_RF1	
Erstellt am: Zuletzt geändert am:	Lode 26.11.2009 13:18:30 26.11.2009 13:18:30		26 11 2009 13:18:30	
Kommentar:				
ОК			Abbrechen	Hilfe

Open DB47 and add UDT21 for each request

Open DB47 and for Reader1, insert the UDT21 five times by means of ARRAY format. For Reader2, also insert UDT21 five times by means of ARRAY format.

Adresse	Name	Тур	Anfangswert	Kommentar
*0.0		STRUCT		
+0.0	Kanal_l_Befehl	ARRAY[15]		SLG1 Aufträge 1 bis 5
*10.0		"MOBY CMD_d"		
+50.0	Kanal_2_Befehl	ARRAY[15]		SLG2 Aufträge 1 bis 5
*10.0		"MOBY CMD_d"		
=100.0		END_STRUCT		



Note

In our example, five request commands are possible for each reader or channel. Thus, the UDT21 is embedded in DB47 10 times. The commands or requests of the second reader start with address 50.



Data View of DB47

Adresse	Name	TYP	Anfangswert	Aktualwert	Kommentar
0.0	Kanal_1_Befehl[1].command	BYTE	B#16#2	B#16#2	WDS Befehl:l=schreiben,2=lesen,3=init,4=slg-status,8=end,A=set-ant,B=mds-status
1.0	Kanal_l_Befehl[1].sub_command	BYTE	B#16#0	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-ANT,MDS-STATUS,SIG-STATUS
2.C	Kanal_l_Befehl[1].length	IMI	T	TR	Anzahl der zu schreibenden/lesenden Daten in Bytes
4.0	Kanal_1_Befehl[1].address_MDS	WORD	W#16#0	W#16#0	Anfangsadresse auf MDS; Endadresse bei INIT;KW/Jahr für MDS-STATUS
6.0	Kanal_l_Befehl[1].DAT_DB_number	IMI	48	48	Wummer des DAT DB; Daten DB für MDS Daten
8.0	Kanal_l_Befehl[1].DAT_DB_address	INI	0	0	Zeiger auf das Anfangswort im DAT DB
10.0	Kanal_1_Befehl[2].command	BYTE	B#16#2	B#16#2	WDS Befehl:l=schreiben,2=lesen,3=init,4=s1g-status,8=end,A=set-ant,B=mds-status
11.0	Kanal_l_Befehl[2].sub_command	BYTE	B#16#0	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-AMT,MDS-STATUS,SLC-STATUS
12.0	Kanal_l_Befehl[2].length	INT	T	1	Anzahl der zu schreibenden/lesenden Daten in Bytes
14.0	Kanal_1_Befehl[2].address_MDS	WORD	W#16#0	W#16#0	Anfangsadresse auf MDS; Endadresse bei INIT;EW/Jahr für MDS-STATUS
16.0	Kanal_1_Befehl[2].DAT_DB_number	IMI	48	48	Nummer des DAT DB; Daten DB für MDS Daten
18.0	Kanal_l_Befeh1[2].DAT_DB_address	IMI	0	0	Zeiger auf das Anfangswort im DAT DB
20.0	Kanal_1_Befehl[3].command	BYTE	B#16#2	B#16#2	MDS Befehl:l=schreiben,2=lesen,3=init,4=slg-status,8=end,A=set-ant,B=mds-status
21.0	Kanal_l_Befehl[3].sub_command	BYTE	D#JT6#0	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-ANT,NDS-STATUS,SLG-STATUS
22.0	Kanal_l_Befehl[3].length	INI	т	T	Anzahl der zu schreibenden/lesenden Daten in Bytes
24.0	Kanal_l_Befehl[3].address_MDS	WORD	0#9T#M	0#JT#N	Anfangsadresse auf MDS; Endadresse bei INIT;KW/Jahr für MDS-STATUS
26.0	Kanal_1_Befehl[3].DAT_DB_number	INT	48	48	Wunner des DAT DB; Daten DB für MDS Daten
28.0	Kanal_1_Befehl[3].DAT_DB_address	INI	0	0	Zeiger auf das Anfangswort im DAT DB
30.0	Kanal_l_Befehl[4].command	BYTE	B#16#2	B#16#2	WDS Befehl:l=schreiben,Z=lesen,3=init,4=slg-status,8=end,A=set-ant,B=mds-status
31.0	Kanal_l_Befeh1[4].sub_command	BYTE	B#16#0	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-ANT,MDS-STATUS,SLG-STATUS
32.0	Kanal_1_Befehl[4].length	IMT	1	I	Anzahl der zu schreibenden/lesenden Daten in Bytes
34.0	Kanal_l_Befehl[4].address_MDS	WORD	0#9T#M	D#JE#0	Anfangsadresse auf MDS; Endadresse bei INIT;KW/Jahr für MDS-STATUS
36.0	Kanal_1_Befehl[4].DAT_DB_number	INI	48	48	Nummer des DAT DB; Daten DB für MDS Daten
38.0	Kanal_l_Befehl[4].DAT_DB_address	INI	0	0	Zeiger auf das Anfangswort im DAT DB
40.0	Kanal_1_Befehl[5].command	BYTE	B#16#2	B#16#2	WDS Befehl:l=schreiben,2=lesen,3=init,4=slg-status,8=end,A=set-ant,B=mds-status
41.0	Kanal_1_Befehl[5].sub_command	BYTE	B#16#0	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-ANT,MDS-STATUS,SLG-STATUS
42.0	Kanal_1_Befehl[5].length	IMI	1	i I	Anzahl der zu schreibenden/lesenden Daten in Bytes
44.0	Kanal_1_Befehl[5].address_MDS	WORD	W#16#0	W#16#0	Anfangsadresse auf NDS; Endadresse bei INIT;KW/Jahr für NDS-STATUS
46.0	Kanal_l_Befehl[5].DAT_DB_number	INI	48	48	Wummer des DAT DB; Daten DB für MDS Daten
48.0	Kanal_l_Befehl[5].DAT_DB_address	INI	0	0	Zeiger auf das Anfangswort im DAT DB
50.0	Kanal_2_Befehl[1].command	BYTE	B#16#2	B#16#2	MDS Befehl:l=schreiben,2=lesen,3=init,4=slg-status,8=end,Å=set-ant,B=mds-status
51.C	Kanal_2_Befehl[1].sub_command	BYTE	B#16#0	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-ANT,MDS-STATUS,SLG-STATUS
52.0	Kanal_2_Befehl[1].length	INI	I	1	Anzahl der zu schreibenden/lesenden Daten in Bytes
54.0	Kanal_2_Befehl[1].address_MDS	WORD	W#16#0	W#16#0	Anfangsadresse auf MDS; Endadresse bei INIT;KW/Jahr für MDS-STATUS
56.0	Kanal_2_Befehl[1].DAT_DB_number	INI	48	48	Wunner des DAT DB; Daten DB für MDS Daten
58.0	Kanal_2_Befehl[1].DAT_DB_address	INT	0	0	Zeiger auf das Anfangswort im DAT DB
60.0	Kanal_2_Befehl[2].command	BYTE	B#16#2	B#16#2	MDS Befehl:1=schreiben,2=lesen,3=init,4=slg-status,8=end,A=set-ant,B=nds-status
61.0	Ranal_2_Befehl[2].sub_command	BYTE	B#16#0	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-ANT,MDS-STATUS,SLG-STATUS

(Starting with byte 50, the commands for Reader2 or channel 2 start)

Save and close DB47

DB45 Reader Parameter Block

Each MOBY channel (reader) needs its own parameters. These are predefined in a data structure as UDT 10 (with English comments), UDT 11 (with German comments) and UDT 14 (with Spanish comments). This UDT has to be called for each MOBY channel in a data block. In UDT 11, different variables are defined:

• INPUT parameters: The user has to enter these variables once during configuration (exception: command_DB_number/command_DB_address). It is not necessary to change or poll these parameters during the entire execution time.

Please note that when an INPUT parameter is changed, an init_run has to be performed before the new setting takes effect (refer to chapter "Programming Restarts and Warm Restarts").

- Control bits: With these Boolean variables, the user starts his commands.
- Displays: The displays show the user the progress of his commands. Errors are easy to analyze.

• Internal FB variables: These variables are of no significance to the user. They must not be changed by the application. Otherwise, malfunction and data corruptions would be the result.



1

Generating DB45

igenschaften - Datenl	paustein	
Allgemein - Teil1 Allgemei	in - Teil 2 Aufrufe Attribute	
Name:	DB45	
Symbolischer Name:	SLG_PARAMETER	_
Symbolkommentar:	hier findet man die Paramete	r zu den SLGs
Erstellsprache:	DB	
Projektpfad:	RFID_RF180C\SIMATIC 300 (2)\Bausteine\DB45	D(1)\CPU 315F-2 PN/DP\S7-Programm
Speicherort des Projekts:	C:\Program Files\Siemens\S	tep7\s7proj\RFID_R_5
Erstellt am:	Code 06.12.2009 15:42:30	Schnittstelle
Zuletzt geändert am:	06.12.2009 15:45:20	06.12.2009 15:45:20
Kommentar:		
ОК	r.	Abbrechen Hilfe

Open DB45 and insert UDT11 for each reader

In DB45, UDT11 is called for each reader

Adresse	Name	Тур	Anfangswert	Kommentar
0.0		STRUCT		
+0.0	SLG_1	"MOBY Param_d"		Parameter des ersten SLG
+50.0	SLG_2	"MOBY Param_d"		Parameter des zweiten SLG
=100.0		END_STRUCT		



Entries in DB45

The base address for the RF180C is 256 (refer to hardware), here to be entered at address 0.0 and $50.0\,$

The selection of Reader1 has to be entered under address 2.0. The selection of Reader2 has to be entered under address 52.0.

DB47 (request data block) is referred to in DB45.

The requests of the first reader have to be entered in DB47 starting with DBB0, here at address 4.0 and 6.0

The requests of the second reader have to be entered in DB47 starting with DBB50, here at address 54.0 and 56.0.

No other values are changed.

For the entries in DB45, take note that the DBs continue to be chained correctly.

Data view of DB45 to byte 33:

Adresse	Name	Typ	Anfangswert	Aktualwert	Kommentar
0.0	SLG_1.ASM_address	INT	256	256	Input: Basisadresse des ASM (zyklisches Wort)
2.0	SLG_1.ASM_channel	INT	1	1	Input: Nummer des Kanals (1 4)
4.0	SLG_1.command_DB_number	INT	47	47	Input: Befehlsdatenbaustein-Nummer
6.0	SLG_1.command_DB_address	INT	0	0	Input: Anfangsadresse der Daten im BEDB
8.0	SLG_1.MDS_control	BYTE	B#16#1	B#16#1	Input: Anwesenheitskontrolle und MDS-Steuerung (0, 1, 2)
9.0	SLG_1.ECC_mode	BOOL	FALSE	FALSE	Input: Betriebsart mit ECC
9.1	SLG_1.RESET_long	BOOL	TRUE	TRUE	Input: true: langes RESET-Telegramm, nur für MOBY-Mode 5, 6
10.0	SLG_1.MOBY_mode	BYTE	B#16#5	B#16#5	Input: MOBY-Betriebsart
11.0	SLG_1.scanning_time	BYTE	B#16#0	B#16#0	Input: Abtastzeit für MOBY I/U
12.0	SLG_1.option_1	BYTE	B#16#0	B#16#0	Input: RESET-Befehl Option 1
13.0	SLG_1.distance_limiting	BYTE	B#16#F	B#16#F	Input: Reichweitenbegrenzung
14.0	SLG_1.multitag	BYTE	B#16#1	B#16#1	Input: max. Anzahl MDS im Feld
15.0	SLG_1.field_ON_control	BYTE	B#16#0	B#16#0	Input: BERO-Betriebsart
16.0	SLG_1.field_ON_time	BYTE	B#16#0	B#16#0	Input: BER0-Zeit
17.0	SLG_1.reserved	BYTE	B#16#0	B#16#0	
18.0	SLG_1.ANZ_MDS_present	BOOL	FALSE	FALSE	Anwesenheit eines MDS
18.1	SLG_1.ANZ_cancel	BOOL	FALSE	FALSE	Cancel-Bit im PEW ist gesetzt
18.2	SLG_1.ANZ_ECC	BOOL	FALSE	FALSE	Fehlerkorrektur wurde durchgeführt
18.3	SLG_1.reserved0	BOOL	FALSE	FALSE	
18.4	SLG_1.LR_bat	BOOL	FALSE	FALSE	Batterie des MDS 507
18.5	SLG_1.battery_low	BOOL	FALSE	FALSE	Batterieüberwachung
18.6	SLG_1.error	BOOL	FALSE	FALSE	Fehler während der Befehlsbearbeitung
18.7	SLG_1.ready	BOOL	FALSE	FALSE	Der Befehl bzw. Befehlskette ist ausgeführt
19.0	SLG_1.cancel	BOOL	FALSE	FALSE	Set: Befehl bzw. Befehlskette abbrechen
19.1	SLG_1.command_start	BOOL	FALSE	FALSE	Set: Startsignal für Befehl bzw. Befehlskette
19.2	SLG_1.repeat_command	BOOL	FALSE	FALSE	Set: Letzten Befehl wiederholen
19.3	SLG_1.init_run	BOOL	TRUE	TRUE	Set: ASM rücksetzen und neu parametrieren
19.4	SLG_1.ASM_failure	BOOL	FALSE	FALSE	OB122 Set: ASM ausgefallen
19.5	SLG_1.FB45_active	BOOL	FALSE	FALSE	FC-aktiv
19.6	SLG_1.ANZ_next	BOOL	FALSE	FALSE	Befehl NEXT war letzter Befehl
19.7	SLG_1.ANZ_reset	BOOL	FALSE	FALSE	Befehl RESET war letzter Befehl
20.0	SLG_1.ASM_busy	BOOL	FALSE	FALSE	ASM bearbeitet einen Befehl
20.1	SLG_1.command_rep_active	BOOL	FALSE	FALSE	ASM führt Befehlswiederholung durch
21.0	SLG_1.number_MDS	BYTE	B#16#0	B#16#0	Anzahl der im Feld befindlichen MDS
22.0	SLG_1.error_MOBY	BYTE	B#16#0	B#16#0	Fehleranzeige vom Anschaltmodul
23.0	SLG_1.error_FB	BYTE	B#16#0	B#16#0	Fehleranzeige von FC
24.0	SLG_1.error_BUS	WORD	W#16#0	W#16#0	Fehleranzeige von PROFIBUS
26.0	SLG_1.version_MOBY	WORD	W#16#0	W#16#0	Firmwareversion MOBY
28.0	SLG_1.counter_customer	BYTE	B#16#0	B#16#0	Interner Schleifenzähler
29.0	SLG_1.counter_notused	BYTE	B#16#0	B#16#0	FB intern
30.0	SLG_1.reserved1[1]	DWORD	DW#16#0	DW#16#0	FB-interne Variablen. Diese dürfen vom Anwender nicht verändert werden.



Data view of DB45 starting with byte 34 (SLG = Reader)

34.0	SLG 1.reserved1[2]	DWORD	DW#16#0	DW#16#0	
38.0	SLG 1. reserved1[3]	DWORD	DW#16#0	DW#16#0	
42.0	SLG 1. reserved2	WORD	W#16#0	W#16#0	FB intern
44.0	SLG 1. initRUN timeout	INT	1000	1000	FB intern
46.0	SLG 1. PEW timout ASM fail	BYTE	B#16#5	B#16#5	FB intern
47.0	SLG 1. PEW timeout	BYTE	B#16#32	B#16#32	FB intern
48.0	SLG 1.reserved3	BYTE	B#16#0	B#16#0	FB intern
49.0	SLG 1. Testbyte	BYTE	B#16#0	B#16#0	FB intern
50.0	SLG 2.ASM address	INT	256	256	Input: Basisadresse des ASM (zyklisches Wort)
52.0	SLG 2.ASM channel	INT	1	2	Input: Nummer des Kanals (1 4)
54.0	SLG 2.command DB number	INT	47	47	Input: Befehlsdatenbaustein-Nummer
56.0	SLG_2.command_DB_address	INT	0	50	Input: Anfangsadresse der Daten im BEDB
58.0	SLG_2.MDS_control	BYTE	B#16#1	B#16#1	Input: Anwesenheitskontrolle und MDS-Steuerung (0, 1, 2)
59.0	SLG_2.ECC_mode	BOOL	FALSE	FALSE	Input: Betriebsart mit ECC
59.1	SLG_2.RESET_long	BOOL	TRUE	TRUE	Input: true: langes RESET-Telegramm, nur für MOBY-Mode 5, 6
60.0	SLG_2.MOBY_mode	BYTE	B#16#5	B#16#5	Input: MOBY-Betriebsart
61.0	SLG_2.scanning_time	BYTE	B#16#0	B#16#0	Input: Abtastzeit für MOBY I/U
62.0	SLG_2.option_1	BYTE	B#16#0	B#16#0	Input: RESET-Befehl Option 1
63.0	SLG_2.distance_limiting	BYTE	B#16#F	B#16#F	Input: Reichweitenbegrenzung
64.0	SLG_2.multitag	BYTE	B#16#1	B#16#1	Input: max. Anzahl MDS im Feld
65.0	SLG_2.field_ON_control	BYTE	B#16#0	B#16#0	Input: BER0-Betriebsart
66.0	SLG_2.field_ON_time	BYTE	B#16#0	B#16#0	Input: BERO-Zeit
67.0	SLG_2.reserved	BYTE	B#16#0	B#16#0	
68.0	SLG_2.ANZ_MDS_present	BOOL	FALSE	FALSE	Anwesenheit eines MDS
68.1	SLG_2.ANZ_cancel	BOOL	FALSE	FALSE	Cancel-Bit im PEW ist gesetzt
68.2	SLG_2.ANZ_ECC	BOOL	FALSE	FALSE	Fehlerkorrektur wurde durchgeführt
68.3	SLG_2.reserved0	BOOL	FALSE	FALSE	
68.4	SLG_2.LR_bat	BOOL	FALSE	FALSE	Batterie des MDS 507
68.5	SLG_2.battery_low	BOOL	FALSE	FALSE	Batterieüberwachung
68.6	SLG_2.error	BOOL	FALSE	FALSE	Fenler wahrend der Befehlsbearbeitung
68.7	SLG_2.ready	BOOL	FALSE	FALSE	Der Befeni bzw. Befeniskette ist ausgefunrt
69.0	SLG_2.cancel	BOOL	FALSE	FALSE	Set: Sefeni bzw. Bereniskette abbrechen
69.1	SLG_2. command_scart	ROOL	PALOE	PALSE	Set: lotation Defebl wiederbelen
69.2	SIG 2 init run	BOOL	TDUE	TDUR	Set. 199 rücksetzen und neu neremetrieren
69.4	SLC 2 ASM failura	BOOL	FALSE	FALSE	OB122 Sat. 15M augustallan
69.5	SLG 2 FB45 active	BOOL	FALSE	FALSE	FC-aktiv
69.6	SLG 2 ANZ next	BOOL	FALSE	FALSE	Refehl NEXT war letzter Befehl
69.7	SLG 2. ANZ reset	BOOL	FALSE	FALSE	Befehl RESET war letzter Befehl
70.0	SLG 2. ASM busy	BOOL	FALSE	FALSE	ASN bearbeitet einen Befehl
70.1	SLG 2.command rep active	BOOL	FALSE	FALSE	ASM führt Befehlswiederholung durch
71.0	SLG 2.number MDS	BYTE	B#16#0	B#16#0	Anzahl der im Feld befindlichen MDS
72.0	SLG_2.error_MOBY	BYTE	B#16#0	B#16#0	Fehleranzeige vom Anschaltmodul
73.0	SLG_2.error_FB	BYTE	B#16#0	B#16#0	Fehleranzeige von FC
74.0	SLG_2.error_BUS	WORD	W#16#0	W#16#0	Fehleranzeige von PROFIBUS
76.0	SLG_2.version_MOBY	WORD	W#16#0	W#16#0	Firmwareversion MOBY
78.0	SLG_2.counter_customer	BYTE	B#16#0	B#16#0	Interner Schleifenzähler
79.0	SLG_2.counter_notused	BYTE	B#16#0	B#16#0	FB intern
80.0	SLG_2.reserved1[1]	DWORD	DW#16#0	DW#16#0	FB-interne Variablen. Diese dürfen vom Anwender nicht verändert werden.
84.0	SLG_2.reserved1[2]	DWORD	DW#16#0	DW#16#0	
88.0	SLG_2.reserved1[3]	DWORD	DW#16#0	DW#16#0	
92.0	SLG_2.reserved2	WORD	W#16#0	W#16#0	FB intern
94.0	SLG_2.initRUN_timeout	INT	1000	1000	FB intern
96.0	SLG_2.PEW_timout_ASM_fail	BYTE	B#16#5	B#16#5	FB intern
97.0	SLG_2.PEW_timeout	BYTE	B#16#32	B#16#32	FB intern
98.0	SLG_2.reserved3	BYTE	B#16#0	B#16#0	FB intern
99.0	SLG_2.Testbyte	BYTE	B#16#0	B#16#0	FB intern

Save and close DB45



Note

The inputs in the data block are entered as actual value.

Take note that when the data block is initialized or a general reset is performed on the CPU, the actual values are overwritten with the start values of the data blocks.

Additional information about setting up the data structure with data blocks and about the individual UDTs is provided in the function manual "RFID Systems FB45".

5.6 Programming a Restart or Warm Restart

1

A restart of the MOBYIM (interface module) is carried out by setting the variable "init_run". With "init_run", the IM and FB45 are re-parameterized and synchronized.

"init_run" is necessary after the following:

- Switching on the SIMATIC (OB 100)
- Switching on the power supply for the IM
- PROFINET communication is interrupted
- An error indication by the variable "error_BUS"
- A transponder type change; for example from RF300 to ISO or vice versa
- Changing an INPUT parameter in DB45 (Reader_Parameter)



Generating OB100

Eigenschaften - Organi	isationsbaustein		×
Allgemein - Teil 1 Allgeme	in - Teil 2 Aufrufe Attribut	e	
Name:	OB100		
Symbolischer Name:	NEUSTART		
Symbolkommentar:	Programmierung von Neust	art und Wiederanlauf	
Erstellsprache:	FUP		
Projektpfad:	Γ		
Speicherort des Projekts:	C:\Program Files\Siemens\	Step7\s7proj\RFID_RF1	
Erstellt am: Zuletzt geöndert am:	Code 26.11.2009 17:35:45 26.11.2009 17:35:45	Schnittstelle	
Kommentar:	26.11.2003 17.30.45	26.11.2003 17.33.43	
ОК	1	Abbrechen	

Open OB100 and enter the program

OB100 : Neustart und Wiederanlauf

Kommentar:						
Netzwerk 1	: Setzen der Variablen "init_run"					
Kommentar:						
SET S S	"SLG_PARAMETER".SLG_1.init_run "SLG_PARAMETER".SLG_2.init_run	DB45.DBX19.3 DB45.DBX69.3	Set: ASM Set: ASM	rücksetzen rücksetzen	und neu und neu	parametrieren parametrieren

Save and close OB100

5.7 FC11 Function for a Command or Request

SIEMENS

Before starting a MOBY command with **"command_start**", we have to define it. For a simple definition of a command, UDT 21 (German comments) is provided. UDT21 is embedded in DB47 multiple times.

So that not all inputs have to be carried out in DB47, here a block for one command or request is generated.

It is then possible to call this block in the control program multiple times; for example for a command string.



i

Generating Function FC11

Set up a new FC11 function.

igenschaften - Funkti	ion					
Allgemein - Teil1 Allgeme	in - Teil 2 Aufrufe Attribute					
Name:	FC11					
Symbolischer Name:	AUFTRAG_BEFEHL	_				
Symbolkommentar:	Baustein für einen Auftrag b	zw. Befehl				
Erstellsprache:	FUP					
Projektpfad:	RFID_IEC_Teil2\SIMATIC 3 Programm(1)\Bausteine\FC1	00(1)\CPU 315F-2 PN/DP\S7- 1				
Speicherort des Projekts:	C:\Program Files\Siemens\Step7\s7proj\RFID_I_1					
Frstellt am	Code 03 12 2009 18:58:48	Schnittstelle				
Zuletzt geändert am:	03.12.2009 17:46:22	03.12.2009 17:46:22				
Kommentar.		2				
OK	J	Abbrechen Hilfe				

Set up IN variables

	Ir	halt von: 'Umgebung\Schn:	ittstelle\IN	L.
🖃 🕕 Schnittstelle	^	Name	Datentyp	Kommentar
		🕲 slg_command	Byte	
🖂 🖾 slg_command		🕲 slg_sub_command	Byte	
🖾 slg_sub_command		🕲 in_length	Int	
🖾 in_length	≣	🕲 in_mds_ADDR	Int	
─ 🖾 in_mds_ADDR		🕲 in_dat_DB_Nr	Int	
──10 in_dat_DB_Nr		🕲 in_dat_DB_ADDR	Int	
I in_dat_DB_ADDR				

Set up OUT variables

	In	hal	t von: 'Ungebung\So	chnittstelle	\OUT'
Ē. -≣ - IN	~		Name	Datentyp	Kommentar
Ė⊶ ⊒- out		12	command	Byte	
- 🖾 conmand		122	sub_command	Byte	
🗝 🖾 sub_command		12	out_length	Int	
🔤 out_length	≣	122	out_mds_ADDR	Word	
… ≌ out_mds_ADDR		12	out_dat_DB_Nr	Int	
🖂 🖾 out_dat_DB_Nr		122	out_dat_DB_ADDR	Int	
□ out_dat_DB_ADDR		Ð			



Enter Networks 1 to 6

FC11 : Request or command

Network 1 Command



Network 2 Sub_Command



Network 3 Data Length



Network 4 MDS start address



Network 5 DB number for data storage destination or source



Network 6 Destination or target address of the DB of data storage



Save and close FC11

5.8 Basics of Entries at Command Block FC11

i

The values for DB47 are specified by means of the input variables of FC11. One UDT21 is used for each request or command.

Data View of the UDT21

Adres	se	Name	Тур	Anfangswert	Kommentar
	0.0		STRUCT		
+	0.0	command	BYTE	B#16#2	MDS Befehl:l=schreiben,2=lesen,3=init,4=slg-status,8=end,A=set-ant,B=mds-status
+	1.0	sub_command	BYTE	B#16#0	Bitmuster für INIT-Befehl; Modus für END,SET-ANT,MDS-STATUS,SLG-STATUS
+	2.0	length	INT	1	Anzahl der zu schreibenden/lesenden Daten in Bytes
+	4.0	address_MDS	WORD	W#16#0	Anfangsadresse auf MDS; Endadresse bei INIT;KW/Jahr für MDS-STATUS
+	6.0	DAT_DB_number	INT	48	Nummer des DAT DB; Daten DB für MDS Daten
+	8.0	DAT_DB_address	INT	0	Zeiger auf das Anfangswort im DAT DB
=1	0.0		END_ST:		

Command Overview

Command (hex)		Command		
Normal	Chained*			
01	41	Write data to MDS		
02	42	Read data from MDS		
03	43	Initialize MDS		
04	44	Reader status		
06		NEXT		
08	08 48 END; end communication with the MDS			
0A	4A	Aerial on/off		
0B	0B 4B MDS status			
*) Not all reader	s or IM modules su	pport chained commands. Note the information in the MOBY		
manuals for con	figuration, installatio	on and service.		

Writing data to the transponder

Command	Sub_command	length	address_MDS [hex]	DAT_DB [dec]	Comment
(hex)		[dec]			
01	-	1 to 32767 *	0000 to FFFF	Pointer to the	
		Length of the	Starting with this	user data that	
		MSD data to be	start address, the	is to be written	
		written	data is written to the	to the MDS	
			MDS		

Reading data from the transponder

Command	Sub_command	length	address_MDS	DAT_DB	Comment
(hex)		[dec]	[hex]	[dec]	
02	-	1 to 32767 *	0000 to FFFF	Pointer to the	
		Length of the	Starting with this	user data.	
		MSD data to be	start address, the	Here, FB45	
		read	data is read from	stores the	
			the MDS	MDS data that	



	was read.	
--	-----------	--



Initialize Transponder

Command	Sub_command	length	address_MDS [hex]	DAT_DB [dec]	Comment
(hex)		[dec]			
03	00 to FF hex	-	Memory size of the	-	
	value that is		MDS to be initialized		
	written to the				
	MDS				

Read out Reader status

Command	Sub_command	length	address_MDS [hex]	DAT_DB [dec]	Comment
(hex)		[dec]			
04	01 = status according to			Pointer to the	MOBY U/D or
	UDT 110 ¹			result. The	RF300
	02 = status according to			result is	MOBY U
	UDT 120 ¹ (last			represented	
	commands)			with the	MOBY U
	03 = status according to			corresponding	
	UDT 130 ¹ (error			UDT (refer to	
	04 = status according to			sub_command	
	UDT 140 ¹ (MDS in the)	
	field)				MOBY U
	05 = status according to				
	UDT 150 (communication				
	quality)				RF300
	06 = status according to				
	UDT 280 (diagnosis data)				

(In our example, we are using the German language UDT111 and UDT281 for RF300)

Command NEXT

Command	Sub_command	length	address_MDS	DAT_DB	Comment
(hex)		[dec]	[hex]	[dec]	
06	-	-	-	-	NEXT: processing
					this MDS is
					completed

Command END

Command	Sub_command	length	address_MDS	DAT_DB	Comment
(hex)		[dec]	[hex]	[dec]	
08	00 = Processing	-	-	-	ANZ_MDS_present
	with the MDS is				is reset
	ended				
	01 = Processing				ANZ_MDS_present

Industry Automation and Drive Technologies - SCE

pause with the		remains set
MDS ¹		

i

Switching the reader aerial on/off

Command	Sub_command	length	address_MDS	DAT_DB	Comment
(hex)		[dec]	[hex]	[dec]	
0A	01 = switch on aerial	-	-	-	The command Aerial
	02 = standby:				on/off can not be started
	Switch aerial off				with command repetition
					(refer to chapter
					"Command Repetition)
	09 = adjust aerial to				Only Reader 80 (MOBY
	the environment (FFT)				F)

Transponder Status

Command	Sub_command	length	address_MDS [hex]	DAT_DB [dec]	Comment
(hex)		[dec]			
0B	00 = status and	-	Today's date	Pointer to	only MOBY U
	diagnosis		(week/year) to	result. The	(refer to
			calculate the life of	result is	chapter "The
			the battery (for	represented	UDTs of
			example, 1401 hex	with UDT 100	FB45")
			= 20th week of year		
			2001)		
	01 = type and write	-	-	Pointer to	RF 300
	protection status			result. The	(refer to
				result is	chapter "The
				represented	UDTs of
				with UDT 260	FB45")
	02 = diagnosis data	-	-	Pointer to	RF 300
				result. The	(refer to
				result is	chapter "The
				represented	UDTs of
				with UDT 270	FB45")

(In our example, we are using the German language UDT261 and UDT271 for RF300)

Notes

5.9 Command String

i

The user configures the command string by storing a corresponding number of UDT 21 one after the other in a DB. All commands that are strung together have to be of the "Command" type "4x". The last command of a string has to be of the type 0x. With it, the FB 45 recognizes the end of a command string.

Example of a command string in DB47

Four data records are to be processed by an MDS. The command structure is stored in the request DB, as shown below. The destination and source data of the MDS are stored consecutively in DB48.

Read MDS address 0000 hex length 600 Read MDS address 1000 hex length 100 Read MDS address 1200 hex length 1 Write MDS address 1200 hex length 1

Name	Initial_Value	Comment
Teilbefehl [1].command Teilbefehl [1].pattern Teilbefehl [1].length Teilbefehl [1].adress_MDS Teilbefehl [1].DAT_DB_number Teilbefehl [1].DAT_DB_address	42 00 600 0000 48 0	Read command, another command follows
Teilbefehl [2].command Teilbefehl [2].pattern Teilbefehl [2].length Teilbefehl [2].adress_MDS Teilbefehl [2].DAT_DB_number Teilbefehl [2].DAT_DB_address	42 00 100 1000 48 600	Read command, another command follows
Teilbefehl [3].command	42	Read command, another command follows
Teilbefehl [3].pattern Teilbefehl [3].length	00	
Teilbefehl [3].adress_MDS	1200	
Teilbefehl [3].DAT_DB_number Teilbefehl [3].DAT_DB_address	48 700	
Teilbefehl [4].command	01	Write command, last command in string
Teilbefehl [4].pattern	00	
I eilbetehl [4].length	1	
Teilbefehl [4].adress_MDS	1200	
Teilbefehl [4].DAT_DB_address	701	

Notes

5.10 Basics of FB45 and DB45

i

FB45 accesses DB45. In DB45, a UDT11 is embedded for each reader.

Data view of the UDT11

Adresse	Name	Тур	Anfangswert	Kommentar
0.0		STRUCT		
10.0	7 CM address	TNII	0	Innut: Designdrosse des ACM
+0.0	ASM_address	TINT	0	(zyklisches Wort)
+2.0	ASM channel	INT	1	Input: Nummer des Kanals (1 4)
+4.0	command DB number	INT	47	Input: Befehlsdatenbaustein-Nummer
+6.0	command_DB_address	INT *	0	Input: Anfangsadresse der Daten im
+8.0	MDS_control	BYTE	B#16#1	Input: Anwesenheitskontrolle und MDS(0, 1, 2)
+9.0	ECC mode	BOOL	FALSE	Input: Betriebsart mit ECC
+9.1	RESET long	BOOL	FALSE	Input: true: langes RESET-
				Telegramm, nur für MOBY-Mode 5
+10.0	MOBY mode	BYTE	B#16#1	Input: MOBY-Betriebsart
+11.0	scanning time	BYTE	B#16#0	Input: Abtastzeit für MOBY I/U
+12.0	option 1	BYTE	B#16#0	Input: RESET-Befehl Option 1
+13.0	distance_limiting	BYTE	B#16#F	Input: Reichweiten- /Leistungseinstellung
+14.0	multitag	BYTE	B#16#1	Input: max. Anzahl MDS im Feld
+15.0	field ON control	BYTE	B#16#0	Input: BERO
+16.0	field_ON_time	BYTE	B#16#0	Input: MOBY U: BERO-Zeit MOBY D: MDS-Typ
+17.0	reserved0	BYTE	B#16#0	
+18.0	ANZ MDS present	BOOL	FALSE	Anwesenheit eines MDSs
+18.1	ANZ cancel	BOOL	FALSE	Cancel-Bit im PEW ist gesetzt
+18.2	ANZ_ECC	BOOL	FALSE	Fehlerkorrektur wurde durchgeführt
+18.3	reserved	BOOL	FALSE	
+18.4	LB bat	BOOL	FALSE	Batterie des MDS 507
+18.5	battery low	BOOL	FALSE	Batterieüberwachung
+18.6	error	BOOL	FALSE	Fehler während der
+18 7	ready	BOOL	FALSE	Befehlsbearbeitung
110.0	ready	BOOL	PALOE	ausgeführt
+19.0	cancei	BOOL	FALSE	abbrechen
+19.1	command_start	BOOL	FALSE	Set: Startsignal für Befehl bzw. Befehlskette
+19.2	repeat_command	BOOL	FALSE	Set: letzten Befehl wiederholen
+19.3	init_run	BOOL	TRUE	Set: ASM rücksetzen und neu parametrieren
+19.4	ASM failure	BOOL	FALSE	OB122 Set: ASM ausgefallen
+19.5	FB45 active	BOOL	FALSE	FB-aktiv
+19.6	ANZ next	BOOL	FALSE	Befehl NEXT war letzter Befehl
+19.7	ANZ reset	BOOL	FALSE	Befehl RESET war letzter Befehl
+20.0	ASM busy	BOOL	FALSE	ASM bearbeitet einen Befehl
+20.1	command_rep_active	BOOL	FALSE	ASM führt Befehlswiederholung durch
+21.0	number_MDS	BYTE	B#16#0	Anzahl der im Feld befindlichen MDS
+22.0	error MOBY	BYTE	B#16#0	Fehleranzeige vom Anschaltmodul
+23.0	error FB	BYTE	B#16#0	Fehleranzeige von FB
+24.0	error BUS	WORD	W#16#0	Fehleranzeige von PROFIBUS
+26.0	version MOBY	WORD	W#16#0	Firmwareversion MOBY
+28.0	reserved2	ARRAY [14]	DW#16#0	FB-interne Variablen. Diese dürfen vom Anwender nicht verändert werden.
*4.0		DWORD		
+44.0	initRUN_timeout	INT	1000	FB-interne Variablen. Diese dürfen vom Anwender nicht verändert
+46.0	PEW_timeout_ASM_fail	BYTE	B#16#5	werden. FB-interne Variablen. Diese dürfen vom Anwender nicht verändert werden
+47.0	PEW_timeout	BYTE	B#16#32	FB-interne Variablen. Diese dürfen vom Anwender nicht verändert werden.
+48.0	reserved3	BYTE	B#16#0	FB-interne Variablen. Diese dürfen vom Anwender nicht verändert werden.
+49.0	Testbyte	BYTE	B#16#0	FB-interne Variablen. Diese dürfen vom Anwender nicht verändert werden.
=50.0		END_STRUCT		

i

Input Parameters of the UDT11

The user has to enter these variables during configuration (exception: command_DB_number/ command_DB_address).

It is not necessary to change or poll these parameters during the entire execution time.

Please note that before the new setting takes effect, "init_run" has to be performed after an INPUT parameter is changed (refer to chapter "Programming Restarts and Warm Restarts").

Variable	Description								
IM Address	IM's logic base address. This address has to match the IM "start address" in HWConfig of the SIMATIC Manager. Please note that this address has nothing to do with the PROFIBUS address that is set at the IM or the ET200M.								
IM Channel	Number of the MOBY channel that is to be used for processing:								
	ASM	Туре	Value Range						
	IM475, 452, 456,RF170C IM 454, 754, 854 ASM 473, 850		1,2, 1,2,3,4 1						
command_DB_ number	Number of data block where the N	IDS command is specified	These INPUT parameters can be changed if ready = 1.						
command_DB_ address	Address within the "command_DB on this address. "command_DB_ "command_DB_address generate command (refer to chapter "Config	Address within the "command_DB". The next MDS command starts on this address. "command_DB_number" and "command_DB_address generate a data pointer to the next command (refer to chapter "Configuration Scheme")							
	Please note: The input parameters command_DB_number and command_DB_address are to be changed only if ready = 1. After changing these parameters, init_run does not have to be performed.								
MDS Control	MDS_control switches the attendance check or the MDS control on or off on the IM (refer to chapter "Attendance Check and MDS Control").								
	Value	MDS Control	ІМ Туре						
	0	Attendance check is switched off. The variable ANZ_MSD_present does not indicate a valid value	All						
	1	Attendance check is switched on. The MDS control is switched off. The variable ANZ_MDS_present indicates an MDS in the transfer window of a reader	All						
	2	Attendance check is switched on. The MDS control is switched on and happens by means of the attendance check of the MDS. The NEXT command has to be sent to the IM after each MDS processing.	454						
ECC_mode	Switches on the ECC mode on (th MOBYI.	Switches on the ECC mode on (true) or off (false). Take note that the ECC mode is permitted only for MOBYI.							
RESET_long	With the command init_run, all INPUT parameters are transmitted to the IM. For MOBY U/D or RF300 operation, this bit has to be set to true (MOBU mode = 5)								

Notes

 Parameter "ASM_address" value = 256 (refer to hardware configuration)

 Parameter "ASM_channel" value = 1 for Reader1

 Parameter "ASM_channel" value = 2 for Reader2

 Parameter "command_DB_number" value = 47 for both readers

 Parameter "command_DB_address" value = 0 for Reader1



Parameter "command_DB_address" Value = 50 for Reader2

i

Variable										
MOBY_mode	Setting	the MOBY Operating								
	Value	Operating Mode	IM Type,							
	0	Default	-; reserved for setting with switch or GSD parameterization: ; different interfaces without switch under- stand under MOBY mode = 0 the MOBY I mode.							
	1	MOBY I or MOBY E (without MDS	All							
	4	MOBY I with MDS 507	452; 454; 456							
	5	MOBY U/D or RF300 – without multi tag hangling	475; 473; 452; 456; RF170C							
	6	Res. for MOBY U – with multi tag handling	-							
	7	Reserved for MOBY D or RF300 - with multi tag handling (FB55)	-							
	8	MOBY I-Dialog	454; 452; 456							
	9	MOBY V	452							
	А	MOBY F with MDS F1xx	475; 473: 452; 854; 850							
	В	MOBY F with MDS F4xx	475; 473: 452; 854; 850							
	С	MOBY F (reserved for MDS	-							
	To be noted: MOBY mode must only be changed after an IM is switched on									
scanning_time	MOBY Scannu MDS tyj scannin Bit	IV: ng_time is the scanning time for the MDS 507 of MO bes, the value 00 can be used.here. The figure below g time (refer also to configguration manual for Reade 7 6 5 4 3 2 1 0 Time value:00 Time factor 00 = 0,01 s 01 = 0,1 s 10 = 1 s 11 = 10 s	BY I and MOBY V. For all other shows the setting for the er 44/MDS 507):							
	Examp (scapni	le: The result of a scanning time of 1 second = 81 h	ex for the parameter ABTA							

Notes

i

Variable			Beschreibung					
scanning_time	MOBY U: Scanning_time beschreibt di scanning_time einen weitere Befehl nach Ablauf der scan verzögert. Eine scanning_time sollte nu • der MDS mit mehreren B • der Bearbeitungsvorgang 00 hex = keine Standby-Zei 01 hex = 7 ms Standby-Zei 02 hex = 14 ms Standby-Zei	e Standby-Ze n Befehl, so k ning_time, so r eingestellt v efehlen beart i in einer mini it (Default) t	it für den MDS. Erhält der MDS vor Ablauf der sann dieser sofort bearbeitet werden. Erhält der MDS einen wird die Befehlsbearbeitung um die sleep_time des MDS verden, wenn beitet wird <i>und</i> malen Zeit abgeschlossen sein muss.					
	: C8 hex = 1400 ms Standby-Zeit Beachte: Die scanning_time beeinflusst die Batterielebensdauer. Je größer die eingestellte scanning_time, desto kürzer die Batterielebensdauer. Genauere Berechnungen finden Sie im MOBY U-Handbuch für Projektierung, Montage und Service.							
option 1	MOBY D bzw. RF300: 00 he	x (reserviert) ert Es bat sta	andardmäßig den Wert B#16#0. Es können damit					
distance limiting	Bit 7 6 5 0 ERR/PR LED-Steue (ASM 45 siehe Anhang	5 4 3 2 0 0 0 0 J 0 0 0 J 0 0 0 J 1 1 1 T T T 0	 1 0 1 = Das Blinken der ERR-LED wird durch einen init_run zurückgesetzt (Bei RF300 wird mit dieser Option auch die ERR_LED am Reader zurückgesetzt.) = Ein MDS-Befehl wird mit Fehler zurückgemeldet, wenn sich kein MDS im Feld befindet (nur MOBY I) stbetrieb; darf im normalen Betrieb nicht gesetzt erden (nur MOBY I) 					
distance_limiting	MOBY U: Reichweitenbegre	nzung						
	normale Sendeleistung 05 hex = 0,5 m 0A hex = 1,0 m 0F hex = 1,5 m 14 hex = 2,0 m 19 hex = 2,5 m 1E hex = 3,0 m 23 hex = 3,5 m	85 hex 8A hex 8F hex 91 hex 99 hex 9E hex A3 hex	reduzierte Sendeleistung Die reduzierte Sendeleistung ist einzustellen, wenn mehrere SLG nahe beieinander positioniert sind oder wenn Datenspeicher, die sich in der Nähe eines SLG aufhalten, später oder nicht mehr erkannt werden sollen. Nachteil: Die Feldkeule wird kleiner und damit steht für die Kommunikation weniger Zeit zur Verfügung bzw. es muss genauer positioniert werden.					
	MOBY D: HF-Leistung von 0,5 W bis 10 W in 0,25 W-Schritten 02 hex = 0,5 W : 10 hex = 4 W (default) : 28 hex = 10 W							

Notes

Parameter "**option_1**" value = 2 to reset the red flashing of the error LED at the reader with

"Init_Run" __

Page 44 of 65

Radio Frequency Identification (RFID) with SIMATIC S7-300F-2PN/DP and

1

Variable	Description							
Valiable	2000 pilot							
multitag	MOBY U/D or RF3 values: 1	MOBY U/D or RF300; maximum number of MDS processed in parallel in the field. Permissible values: 1						
field_ON_control	MOBY U: BERO operating mode; aerial field is switched on/off automatically. The command "Aerial ON/OFF" is overlaid by the BERO operating mode.							
	00 hex = Without BEROs; no reader synchronization							
	01 hex	One or two BEROs; The BEROs are logically ored. While a BERO is operated, the field is switched on						
	02 hex	=	One or two BEROs. The 1st BERO switches the field on and the 2nd BERO switches the field off. If there are 2 BEROs <i>and</i> one field_ON_time is parameterized, the field is switched off automatically if the 2nd BERO does not switch within the BERO time. If no field_ON_time is parameterized, the field remains switched on until the 2nd BERO is operated.					
	03 hex	=	Activate reader synchronization by means of cable connection (refer to manual for Configuration, Installation and Service for MOBY U)					
	MOBY D or RF300: 00 hex (reserved)							
field_ON_time	MOBY U: time for	BEF	RO operating mode (field_ON_control = 02)					
	00 hex	=	Time monitoring is switched off. For field switch-off, the 2nd BERO is needed.					
	01 hex FF hex	=	1255s switch-on time for the Reader field					
	MOBY D: MDS ty	ре						
	00 hex	=	I-code 1 (for example, MDS D139)					
	01 hex	=	ISO MDS					
	RF300: 00 hex (re	serv	/ed)					
reserved	Reserved							

Notes

Parameter "field_ON_time" value = 0 for MDS type RF300 _____ Parameter "field_ON_time" value = 1 for MDS type ISO_____





Command and Status Word "BEST"

The control bits of FB45 are defined in the command and status word. The command and status word with the variables is generated with UDT 11. The variables and the associated relative addresses in UDT 11 are shown in the figure below.

Control bits:

The user starts his commands with these Boolean variables.



1

Control bits from Bit0 to Bit7

Variable	Description
cancel	<i>True</i> =interruption of a current command or a command string. FB45 then sets the variable ready. MOBY U/D or RF300 : the variable 'cancel' is not available. A command has to be canceled with the variable init run.
command start	True – start of a command or a command string
repeat_ command	True = command repetition: The command or command chain stored last in the IM is reprocessed with the next MDS. However, command processing for the MDS is started only after the MDS that was processed has exited the transmission window (ANZ_MDS_present= 0) and a new MDS has entered the transmission window of the reader (ANZ_MDS_present: $0 \rightarrow 1$).
	<i>False</i> = no command repetition, or command repetition is stopped after the command that was started with the repeat command is processed. Please note that the user has to reset this bit in order to stop command repetition. The result of the command repetition is fetched by the use setting command_start.
	Repeat_command is not reset automatically by FB45 after the command is processed.
	The commands init_run and cancel reset the variable repeat_command. This also interrupts a command repetition in the IM. repeat_command can be set again by the application with the next command_start. Handling of command repetition is described in the chapter "Command Repetition".
Init_run	<i>True</i> = IM restart. In this case, FB45 is also reset and the IM re-parameterized. All data and commands in the IM are lost. This bit has to be set in the restart OB (OB100) for each MOBY channel or IM. After a MOBY-IM fault, the error error_MOBY=0F is indicated to the user. The user then has to perform an init_run.
	 Please note: When loading a parameter data block from the programming device to the SIMATIC, bit init_run is pre-assigned TRUE. The result is the automatic execution of an IM restart. The time to execute init_run is normally in the millisecond range. If there is an error, this time may extend to 15s.
IM_failure	<i>True</i> = the IM failed. The user sets this bit in OB122 (refer to chapter "Programming Module Failure"). FB45 then signals an error to the user (error_FB = 09) and interrupts the current command. If the user does not program OB122, the PLC enters the STOP mode if the IM fails.
FB45_active	 FB45 is just processing a command. This variable is set when the command is started (command_start=True) and remains active until FB45 has received the last acknowledgement from the IM The init_run bit was set The cancel bit was set The IM signaled an error
ANZ_next	This bit is set if the command executed last was a NEXT command
ANZ_reset	This bit indicates that the command executed last was a RESET. The user started the RESET command with "init_run".

Notes

i

Control bits from Bit8 to Bit15

Variable	Description
ANZ_MDS_present	Indicates the presence of an MDS in the transmission window of the Read/Write MDS. ANZ_MDS_present is indicated only if the user set the INPUT parameter MDS_control. Please note that when init run is executed, the ANZ_MDS_present indication briefly
	disappears even if an MDS stays permanently in the transmission window.
ANZ_cancel	The command executed last was a command interruption (cancel). The bit is set if the IM displays a cancel acknowledgement by means of the cyclical word (refer to chapter "Cyclical Control Word between Master and MOBY IM". Reset is automatic by starting a new command.
ANZ_ECC	Only MOBY I : If the ECC driver is switched on (INPUT parameter "ECC mode" = TRUE), the bit indicates that the data read by the MDS was corrected. ANZ_ECC is <i>not</i> an error indication since the data is OK. ANZ_ECC indicates that in the near future the MDS memory that was just processed may completely fail.
reserved	Presently not assigned
LR_bat	This bit is of significance only if at MOBY I processing takes place with the MDS507. It indicates an empty MDS507 dialog battery. For all other MDSs, this bit can take on any state.
battery_low	Only for MOBY I/V with RAM MDS The back-up battery of the RAM MDS is below the threshold. Although it is still possible to process several months at room temperature with the remaining capacity, it is recommended to immediately change the battery or to replace the MDS if the battery can't be changed.
error	FB45 sets this bit if a command is concluded faulty. The error bit is the sum error bit for all occurring errors. The exact cause for the error is located in the variable error_MOBY, error_FB or error_BUS (refer also to chapter "Additional Indications" or chapter "Error Indications and Error Search"). Restarting the command resets the error bit.
ready	Ready indication: after ready = TRUE was indicated, the error bit = FALSE has to be polled. This ensures that the command was processed without error.
	Please note: The ready bit does not have to be set for starting init_run or cancel.

Notes







Additional indications

The displays indicate to the user the progress of a command. Error analyses are easy to perform.

Variable	Description
IM_busy	This bit is set when the IM processes a command. Normally, "IM_busy" is inverted to "ready". IM_busy is indicated by the IM by means of the cyclical word (refer to chapter "Cyclical Control Word between Master and MOBY IM" under "IM_busy"). If processing takes place with the automatic command start repeat_command, this bit indicates the processing of a new MDS with the command that is to be executed.
command_rep_active	The IM is just executing a command repetition. The bit is set as a response to the control variable repeat_command. After init_run, FB45 first resets the command_rep_active; it is set again delayed since FB45 first transmits the MOBY commands to the IM.
number_MDS	MOBY U/D or RF300 : The number of MDSs is indicated that are presently located in the transmission window. If more than 15 MDSs are in the field, the display number_MDS stops at 0F hex.
error_MOBY	The IM signaled this error. As a rule, this error is indicated also on the ERR LED on the IM channel display (refer to chapter "Error Indications and Error Search").
error_FB	Error indication from FB45 (refer to chapter "Error Indications and Error Search").
error_BUS	The transmission path between FB45 and the IM signals an error. As a rule, this is a PROFIBUS error (refer to chapter "Error Indications and Error Search"). This error is indicated by the system functions SFC 58/59.
version_MOBY	Display of the firmware version of the MOBY IM. The value entered here is updated after every IM power-up . It is ASCII encoded.
	Example: DBB26 DBB27 31 hex $30 hex"1" "0" \rightarrow \text{Version 1.0}$

Notes





All other UDT 11 variables are for internal FB use only. The user must not change them at all.

5.11 FB10 Reader_Control Program



Now, we are going to program the following in FB10: the control program for the control commands of a reader, and the call of FB45.

In addition, the attendance time of the transponder is to be recorded.

Generating FB10

First, set up a new function block FB10.

Eigenschaften - Funkti	ionsbaustein	X						
Allgemein - Teil1 Allgeme	in - Teil 2 Aufrufe Attrib	ute						
Name:	FB10	Multiinstanzfähig						
Symbolischer Name:	SLG_STEUERUNG							
Symbolkommentar:	Steuerbefehle zu einem SLG							
Erstellsprache:	FUP							
Projektpfad:	RFID_RF180C_IEC\SIMATIC 300(1)\CPU 315F-2 PN/DP\S7- Programm(2)\Bausteine\FB10							
Speicherort des Projekts:	C:\Program Files\Siemens\Step7\s7proj\RFID_R_6							
Erstellt am: Zuletzt geändert am:	Code 08.12.2009 18:57:22 08.12.2009 20:07:04	Schnittstelle 08.12.2009 19:04:41						
Kommentar:	SLG-Baustein	<u>×</u>						
ОК		Abbrechen Hilfe						

Then, set up IN variables

Inhalt von: 'Umgebung\Schnittstelle\IN'								
i⊐-∎ IN	~		Name	Datentyp	Adresse	Anfangswert		
🔤 slg_start		1	slg_start	Bool	0.0	FALSE		
🗆 🖻 mds_present		12	mds_present	Bool	0.1	FALSE		
🔤 slg_error		12	slg_error	Bool	0.2	FALSE		
🔤 slg_ready	≣	12	slg_ready	Bool	0.3	FALSE		
E slg_option_l		12	slg_option_l	Byte	1.0	B#16#0		
🐨 🖻 slg_reset		12	slg_reset	Bool	2.0	FALSE		
──`⊡ slg_iso		12	slg_iso	Bool	2.1	FALSE		
🖾 Params_DB		12	Params_DB	Int	4.0	0		
1 Params_ADDR		153	Params_ADDR	Int	6.0	0		

Next, set up OUT variables

Inhalt von: 'Ungebung\Schnittstelle\OUT'								
⊡ ⊶ ⊡ • о∪т	^		Name	Datentyp	Adresse	Anfangsvært		
······································	_	122	command_start	Bool	8.0	FALSE		
─`⊡ option_1		123	option_1	Byte	9.0	B#16#0		
─~`⊡ field_on_time		122	field_on_time	Byte	10.0	B#16#0		
🖓 🖾 init_run		122	init_run	Bool	11.0	FALSE		
🖾 mds_time	_	12	mds_time	Time	12.0	T#OMS		

-



Then, set up STAT variables

Inhalt von: 'Umgebung\Schnittstelle\STAT'								
E	~ [Name	Datentyp	Adresse	Anfangswert		
🖻 fml		3	fml	Bool	16.0	FALSE		
🖻 fm2		1	fm2	Bool	16.1	FALSE		
🖻 fn3		1	fm3	Bool	16.2	FALSE		
🔁 fm4		1	fm4	Bool	16.3	FALSE		
``E fm5		1	fm5	Bool	16.4	FALSE		
🖻 fn6		1	fm6	Bool	16.5	FALSE		
🔤 mds_zeit		1	mds_zeit	Time	18.0	T#OMS		

Next, set up TEMP variables

	In	Inhalt von: 'Umgebung\Schnittstelle\TH						
	~		Name		Datentyp	Adresse		
—	_	12	initl		Bool	0.0		
🖂 🖾 initl		122	init2		Bool	0.1		
🖂 🖾 init2		12	init3		Bool	0.2		
🖾 init3		Ы						

Networks 1 to 3

FB10 : Reader block

Network 1 :Command start



Network 2 : Reset Reader



Network 3: ISO mode





Networks 4 to 8





Network 5 : init_run



Network 6 : Attendance time MDS at reader



Network 7 : Reader1 MDS time evaluaton





Note regarding networks 7and 8:

The switch-on delay **TON (SFB4)** in Network 7 and the **FB45** call in Network 8 are added as multiinstance. After insertion in the program, click on the block with the right mouse key and select "**Change to multi-instance call**".

Then enter the name of the multi-instance in the window (refer to NW7 or NW8 without #).



Save and close FB10

5.12 FB1 Control Program



It is now possible to generate the control program with the completed blocks.

Task:

In our sample program, two command strings with two requests each will be processed.

With the **START_SLG1 (I0.0)**, the command chain of the first reader is executed. First, the MDS status information will be read, and then a write command is carried out on Reader1. With Reader1, we write 8 bytes that are stored in DB48 starting with DBB0 to the MDS. With the **RESET_SLG1** (I0.1), the error is reset if there is an error (LED at Reader1 flashes red) and a "init run command" to reset the first reader is executed.

With the **RF300_ISO** (I02), switching between MDS types (for example RF360T) or ISO transponder (for example, Moby D ISO) is to be carried out on the first reader (RF310R).

With the **START_SLG2** (I1.0), the command string of the second reader is executed. First, the MDS diagnosis information will be read and then a read command will be executed at Reader2. With Reader2, we read 8 bytes from the transponder and then write them to DB48 starting with DBB50.

With **RESET_SLG2** (I1.1) the error is reset if there is an error (LED at SLG2 flashes red) and a "init_run command" is executed to reset the second reader.

In addition, the attendance time of the transponders is to be recorded on the readers.

Supplementing the symbol table

Symbol	Addres	S	Data Type	Comment
START_SLG1	1	0.0	BOOL	Command start of Reader1
RESET_SLG1		0.1	BOOL	Reset Reader1 error
RF300_ISO	1	0.2	BOOL	Value 0 = RF300, Value 1 = ISO
START_SLG2	1	1.0	BOOL	Command start of SLG2
RESET_SLG2	1	1.1	BOOL	Reset Reader2 error
AWZ_SLG1	MD	40	TIME	Attendance time of transponder at SLG1
AWZ_SLG2	MD	50	TIME	Attendance time of transponder at SLG2
STATUS_SLG_1	VAT	1		SLG1 variable table
STATUS_SLG_2	VAT	2		SLG2 variable table



Generating FB1

Set up a new FB1.

Name:	FB1	Multiinstanzfähig		
δymbolischer Name:	STEUERUNGSPROGRAMM			
Symbolkommentar:	Steuerungsprogramm mit Bausteinen			
Erstellsprache:	FUP			
^p rojektpfad:	RFID_RF180C_IEC\SIMATIC 300(1)\CPU 315F-2 PN/DP\S7- Programm(2)\Bausteine\FB1			
peicherort des Projekts:	C:\Program Files\Siemens\	Step7\s7proj\RFID_R_6		
Erstellt am:	Code 08.12.2009 19:05:17	Schnittstelle		
Zuletzt geändert am:	08.12.2009 20:24:43	08.12.2009 19:29:03		
(ommentar:	Steuerungsprogramm	1		



Setting up TEMP Variables

	In	hal	t von: 'Umgebung\	Schnittstel	le\TEMP'
	~		Name	Datentyp	Adresse
		1	init_runl	Bool	0.0
TU_OUT		12	init_run2	Bool	0.1
🛨 🖅 STAT	≡				
+ JEMP					

Network 1 to 2

FB10 is inserted as a multi-instance block.







Network 3

Netzwerk 3 : Auftrag oder Befehl zu SLG1 aufrufen



Page 58 of 65

DB47.DBW14 DB47.DBW16 DB47.DBW18

Radio Frequency Identification (RFID) with SIMATIC S7-300F-2PN/DP and



Network 4 to 5

Netzwerk 4 : Steuerbefehle zu SLG2 aufrufen



Symbolinformation:

START SLG2
"SLG PARAMETER".SLG 2.ANZ MDS present
"SLG PARAMETER".SLG 2.error
"SLG PARAMETER".SLG 2.ready
RESET SLG2
"SLG_PARAMETER".SLG_2.command_start
"SLG PARAMETER".SLG 2.option 1
"SLG PARAMETER".SLG_2.field ON time
AWZ SLG2

E1.0	Befehlsstart des SLG2				
DB45.DBX68.0	Anwesenheit eines MDS				
DB45.DBX68.6	ehler während der Befehlsbearbeitung				
DB45.DBX68.7	Der Befehl bzw. Befehlskette ist ausgeführt				
E1.1	SLG2 Fehler rücksetzen				
DB45.DBX69.1	Set: Startsignal für Befehl bzw. Befehlskett				
DB45.DBB62	Input: RESET-Befehl Option 1				
DB45.DBB66	Input: BERO-Zeit				

-- Anwesenheitszeit des Transpnders am SLG2

für Befehl bzw. Befehlskette

Netzwerk 5 : Set: SLG2 ASM rücksetzen und neu parametrieren



Symbolinformation: "SLG_PARAMETER".SLG_2.init_run

DB45.DBX69.3

MD 50

-- Set: ASM rücksetzen und neu parametrieren



Network 6

Netzwerk 6 : Auftrag oder Befehl zu SLG2 aufrufen



Save and close FB1

Page 60 of 65

Radio Frequency Identification (RFID) with SIMATIC S7-300F-2PN/DP and

5.13 OB1 Program Call



Double click on OB1 in the project window, or open the object properties of OB1 and enter the symbolic name and the symbol comment.

Eigenschaften - Organi	isationsbaustein		X				
Allgemein - Teil1 Allgemei	in - Teil 2 Aufrufe Attribute						
Name:	081						
Symbolischer Name:	PROGRAMMAUFRUF	_					
Symbolkommentar:	Symbolkommentar: Steuerungsprogramm aufrufen						
Erstellsprache:	FUP						
Projektpfad:	RFID_RF180C_IEC\SIMATIC 300(1)\CPU 315F-2 PN/DP\S7- Programm(2)\Bausteine\OB1						
Speicherort des Projekts:	C:\Program Files\Siemens\Step7\s7proj\RFID_R_6						
	Code	Schnittstelle					
Erstellt am:	05.12.2009 16:34:07						
Zuletzt geändert am:	08.12.2009 19:29:24	15.02.1996 16:51:12					
Kommentar:	Steuerungsprogramm aufrufe	n 📩					
ОК		Abbrechen Hilfe					

Open OB1 and call FB1 with DB1

OB1 : Steuerungsprogramm aufrufen							
Kommentar:							
Netzwerk 1): FB1 aufrufen							
Konnentar:							
DE1 "STEUERUNGSPROGRAMM " EN ENO							
Symbolinformation: STEUERUNGSPROGRAMM FB1	Steuerungsprogramm mit Bausteinen						

Confirm the window with the query for generating DB1 by clicking on "Yes".

Save and close OB1

We can now load the program into the controller and test it.

5.14 Variable Table STATUS_SLG_1



Operand		Symbol	Anzeigeformat	Statuswert	Steuerwert
// Cancel					
DB45.DBX	19.0	"SLG_PARAMETER".SLG_1.cancel	BOOL	false	
// Command	Start				
DB45.DBX	19.1	"SLG_PARAMETER".SLG_1.command_start	BOOL	false	
// System St	art Up	0			
DB45.DBX	19.3	"SLG_PARAMETER".SLG_1.init_run	BOOL	false	
// Ready					
DB45.DBX	18.7	"SLG_PARAMETER".SLG_1.ready	BOOL	true 🛛	
// Presence	of a M	ADS.			
DB45.DBX	18.0	"SLG_PARAMETER".SLG_1.ANZ_MDS_present	BOOL	false	
MD 40		"AWZ_SLG1"	ZEIT	T#5s21ms	
// Error					
DB45.DBX	18.6	"SLG_PARAMETER".SLG_1.error	BOOL	false	
// Errors					
DB45.DBB	22	"SLG_PARAMETER".SLG_1.error_MOBY	HEX	B#16#00	
DB45.DBB	23	"SLG_PARAMETER".SLG_1.error_FB	HEX	B#16#00	
// MOBY Co	mman	d			
DB47.DBB	0	"AUFTRAG".Kanal_1_Befehl[1].command	HEX	B#16#4B	
DB47.DBB	1	"AUFTRAG".Kanal_1_Befehl[1].sub_command	HEX	B#16#01	
DB47.DBW	2	"AUFTRAG".Kanal_1_Befehl[1].length	DEZ	18	
DB47.DBW	4	"AUFTRAG".Kanal_1_Befehl[1].address_MDS	HEX	VV#16#0000	
DB47.DBW	6	"AUFTRAG".Kanal_1_Befehl[1].DAT_DB_number	DEZ	49	
DB47.DBW	8	"AUFTRAG".Kanal_1_Befehl[1].DAT_DB_address	DEZ	0	
DB48.DBB	0	"S_L_DATEN".Daten[1]	ZEICHEN	'R'	'R'
DB48.DBB	1	"S_L_DATEN".Daten[2]	ZEICHEN	'F'	'F'
DB48.DBB	2	"S_L_DATEN".Daten[3]	ZEICHEN	Ψ	T
DB48.DBB	3	"S_L_DATEN".Daten[4]	ZEICHEN	'D'	'D'
DB48.DBB	4	"S_L_DATEN".Daten[5]	ZEICHEN	'T'	'T'
DB48.DBB	5	"S_L_DATEN".Daten[6]	ZEICHEN	'E'	Έ'
DB48.DBB	6	"S_L_DATEN".Daten[7]	ZEICHEN	'S'	'S'
DB48.DBB	7	"S_L_DATEN".Daten[8]	ZEICHEN	'T'	'T'
DB48.DBB	50	"S_L_DATEN".Daten[51]	ZEICHEN	B#16#00	
DB48.DBB	51	"S_L_DATEN".Daten[52]	ZEICHEN	B#16#00	
DB48.DBB	52	"S_L_DATEN".Daten[53]	ZEICHEN	B#16#00	
DB48.DBB	53	"S_L_DATEN".Daten[54]	ZEICHEN	B#16#00	
DB48.DBB	54	"S_L_DATEN".Daten[55]	ZEICHEN	B#16#00	
DB48.DBB	55	"S_L_DATEN".Daten[56]	ZEICHEN	B#16#00	
DB48.DBB	56	"S_L_DATEN".Daten[57]	ZEICHEN	B#16#00	
DB48.DBB	57	"S_L_DATEN".Daten[58]	ZEICHEN	B#16#00	
DB45.DBB	16	"SLG_PARAMETER".SLG_1.field_ON_time	HEX	B#16#00	
DB47.DBB	10	"AUFTRAG".Kanal_1_Befehl[2].command	HEX	B#16#01	
DB47.DBB	11	"AUFTRAG".Kanal_1_Befehl[2].sub_command	HEX	B#16#00	
DB47.DBW	12	"AUFTRAG".Kanal_1_Befehl[2].length	DEZ	8	
DB47.DBW	14	"AUFTRAG".Kanal_1_Befehl[2].address_MDS	HEX	VV#16#0000	
DB47.DBW	16	"AUFTRAG".Kanal_1_Befehl[2].DAT_DB_number	DEZ	48	
DB47.DBW	18	"AUFTRAG".Kanal_1_Befehl[2].DAT_DB_address	DEZ	0	

5.15 Variable Table STATUS_SLG_2



Operand	Symbol	Anzeigeformat	Statuswert	Steuerwert
// Cancel				
DB45.DBX 69.0	"SLG_PARAMETER".SLG_2.cancel	BOOL	false	
// Command Star	I			
DB45.DBX 69.1	"SLG_PARAMETER".SLG_2.command_start	BOOL	false	
// System Start U	p			
DB45.DBX 69.3	"SLG_PARAMETER".SLG_2.init_run	BOOL	false	
// Ready				
DB45.DBX 68.7	"SLG_PARAMETER".SLG_2.ready	BOOL	📙 true	
// Presence of a	MDS			
DB45.DBX 68.0	"SLG_PARAMETER".SLG_2.ANZ_MDS_present	BOOL	false	
MD 50	"AWVZ_SLG2"	ZEIT	T#3s994ms	
// Error				
DB45.DBX 68.6	"SLG_PARAMETER".SLG_2.error	BOOL	false	
// Errors				
DB45.DBB 72	"SLG_PARAMETER".SLG_2.error_MOBY	HEX	B#16#00	
DB45.DBB 73	"SLG_PARAMETER".SLG_2.error_FB	HEX	B#16#00	
// MOBY Comman	nd			
DB47.DBB 50	"AUFTRAG".Kanal_2_Befehl[1].command	HEX	B#16#4B	
DB47.DBB 51	"AUFTRAG".Kanal_2_Befehl[1].sub_command	HEX	B#16#02	
DB47.DBW 52	"AUFTRAG".Kanal_2_Befehl[1].length	DEZ	18	
DB47.DBVV 54	"AUFTRAG".Kanal_2_Befehl[1].address_MDS	HEX	VV#16#0000	
DB47.DBVV 56	"AUFTRAG".Kanal_2_Befehl[1].DAT_DB_number	DEZ	49	
DB47.DBW 58	"AUFTRAG".Kanal_2_Befehl[1].DAT_DB_address	DEZ	18	
DB48.DBB 0	"S_L_DATEN".Daten[1]	ZEICHEN	'R'	
DB48.DBB 1	"S_L_DATEN".Daten[2]	ZEICHEN	'F'	
DB48.DBB 2	"S_L_DATEN".Daten[3]	ZEICHEN	ሞ	
DB48.DBB 3	"S_L_DATEN".Daten[4]	ZEICHEN	'D'	
DB48.DBB 4	"S_L_DATEN".Daten[5]	ZEICHEN	'T'	
DB48.DBB 5	"S_L_DATEN".Daten[6]	ZEICHEN	'E'	
DB48.DBB 6	"S_L_DATEN".Daten[7]	ZEICHEN	'S'	
DB48.DBB 7	"S_L_DATEN".Daten[8]	ZEICHEN	'T'	
DB48.DBB 50	"S_L_DATEN".Daten[51]	ZEICHEN	'R'	
DB48.DBB 51	"S_L_DATEN".Daten[52]	ZEICHEN	'F'	
DB48.DBB 52	"S_L_DATEN".Daten[53]	ZEICHEN	ሞ	
DB48.DBB 53	"S_L_DATEN".Daten[54]	ZEICHEN	'D'	
DB48.DBB 54	"S_L_DATEN".Daten[55]	ZEICHEN	'T'	
DB48.DBB 55	"S_L_DATEN".Daten[56]	ZEICHEN	'E'	
DB48.DBB 56	"S_L_DATEN".Daten[57]	ZEICHEN	'S'	
DB48.DBB 57	"S_L_DATEN".Daten[58]	ZEICHEN	'T'	
DB47.DBB 60	"AUFTRAG".Kanal_2_Befehl[2].command	HEX	B#16#02	
DB47.DBB 61	"AUFTRAG".Kanal_2_Befehl[2].sub_command	HEX	B#16#00	
DB47.DBVV 62	"AUFTRAG".Kanal_2_Befehl[2].length	DEZ	8	
DB47.DBW 64	"AUFTRAG".Kanal_2_Befehl[2].address_MDS	HEX	V \# 16 # 0000	
DB47.DBW 66	"AUFTRAG".Kanal_2_Befehl[2].DAT_DB_number	DEZ	48	
DB47.DBVV 68	"AUFTRAG".Kanal_2_Befehl[2].DAT_DB_address	DEZ	50	

5.16 Symbol Table

1	l
11	
11	۱
H	١

Symbol	Adresse /	Datentyp	Kommentar
SLG_PARAMETER	DB 45	DB 45	hier findet man die Parameter zu den SLGs
AUFTRAG	DB 47	DB 47	hier werden die Kommandos eingegeben
S_L_DATEN	DB 48	DB 48	hier werden die Daten des Schreib-Lese Auftrags eingetragen
MDS_STATUS	DB 49	DB 49	hier werden die MDS-Status Informationen abgelegt
SLG_STATUS	DB 50	DB 50	hier werden die SLG-Status Informationen abgelegt
START_SLG1	E 0.0	BOOL	Befehlsstart des SLG1
RESET_SLG1	E 0.1	BOOL	SLG1 Fehler rücksetzen
RF300_ISO	E 0.2	BOOL	Wert 0 = RF300, Wert 1 = ISO
START_SLG2	E 1.0	BOOL	Befehlsstart des SLG2
RESET_SLG2	E 1.1	BOOL	SLG2 Fehler rücksetzen
STEUERUNGSPROGR	FB 1	FB 1	Steuerungsprogramm mit Bausteinen
SLG_STEUERUNG	FB 10	FB 10	Steuerbefehle zu einem SLG
MOBY FB	FB 45	FB 45	
AUFTRAG_BEFEHL	FC 11	FC 11	Baustein für einen Auftrag bzw. Befehl
AWZ_SLG1	MD 40	TIME	Anwesenheitszeit des Transpnders am SLG1
AWZ_SLG2	MD 50	TIME	Anwesenheitszeit des Transpnders am SLG2
PROGRAMMAUFRUF	08 1	OB 1	Steuerungsprogramm aufrufen
NEUSTART	OB 100	OB 100	Programmierung von Neustart und Wiederanlauf
TON	SFB 4	SFB 4	Generate an On Delay
RDREC	SFB 52	SFB 52	Read a Process Data Record
WRREC	SFB 53	SFB 53	Write a Process Data Record
MOBY Param_d	UDT 11	UDT 11	Parametrier DB
MOBY CMD_d	UDT 21	UDT 21	Command DB Normaladressierung
MOBY SLG-Status_d	UDT 111	UDT 111	MOBY: SLG Status Daten
MOBY P MDS-Status	UDT 261	UDT 261	MOBY P: MDS Status Daten
MOBY P MDS-Status	UDT 271	UDT 271	MOBY P: MDS Status Daten
MOBY P SLG-Status_d	UDT 281	UDT 281	MOBY P: SLG Status Daten
STATUS_SLG_1	VAT 1		Variablentabelle des SLG1
STATUS_SLG_2	VAT 2		Variablentabelle des SLG2

5.17 Block Folder

Objektname	Symbolischer Name	Erstellsprache	Größe im Arbeitsspei	Тур	Versi
🚵 Systemdaten		1000	10 M	SDB	222
🕞 OB1	PROGRAMMAUFRUF	FUP	72	Organisationsbaustein	0.1
🖬 0B100	NEUSTART	AWL	52	Organisationsbaustein	0.1
🕒 FB1	STEUERUNGSPROGRA	FUP	1242	Funktionsbaustein	0.1
🕒 FB10	SLG_STEUERUNG	FUP	346	Funktionsbaustein	0.1
🗗 FB45	MOBY FB	AWL	7846	Funktionsbaustein	1.3
G FC11	AUFTRAG_BEFEHL	FUP	98	Funktion	0.1
🖬 DB1		DB	972	Instanzdatenbaustei	0.0
🗇 DB45	SLG_PARAMETER	DB.	136	Datenbaustein	0.1
🖬 DB47	AUFTRAG	DB	136	Datenbaustein	0.1
🗇 DB48	S_L_DATEN	DB	1060	Datenbaustein	0.1
🕞 DB49	MDS_STATUS	DB	72	Datenbaustein	0.1
🖬 D850	SLG_STATUS	DB	92	Datenbaustein	0.1
🕒 UDT11	MOBY Param_d	AWL		Datentyp	1.3
🖬 UDT21	MOBY CMD_d	AWL		Datentyp	1.3
UDT111	MOBY SLG-Status_d	AWL	121	Datentyp	1.3
🖽 UDT261	MOBY P MDS-Status 0_d	AWL		Datentyp	1.3
UDT271	MOBY P MDS-Status 1_d	AWL	257	Datentyp	1.3
UDT281	MOBY P SLG-Status_d	AWL	772	Datentyp	1.3
TATUS_SLG_1	STATUS_SLG_1			Variablentabelle	1.3
STATUS_SLG_2	STATUS_SLG_2			Variablentabelle	1.3
🗗 SFB4	TON	AWL		Systemfunktionsbau	1.0
SFB52	RDREC	AWL		Systemfunktionsbau	1.0
SFB53	WRREC	AWL		Systemfunktionsbau	1.0

5.18 DB49 Data View

Adresse	Name	Тур	Anfangswert	Aktualwert	Konmentar				
0.0	MDS_Status0.reserved0	BYTE	B#16#0	B#16#01					
1.0	MDS_Status0.status_info	BYTE	B#16#0	B#16#00	Nodus MDS-Status				
2.0	MDS_Status0.UID[1].Byte_1_4	DWORD	DW#16#0	DW#16#00000000	MDS-Nummer (unique identifier)				
6.0	MDS_Status0.UID[1].Byte_5_8	DWORD	DW#16#0	DW#16#557AFEFA					
10.0	MDS_Status0.MDS_type	BYTE	B#16#0	B#16#02	MDS-Typ				
11.0	MDS_Status0.Lock_state	BYTE	B#16#0	B#16#00	Schreibschutzstatus EEPROM				
12.0	MDS_Status0.reserved1[1]	BYTE	B#16#0	B#16#00					
13.0	MDS_Status0.reserved1[2]	BYTE	B#16#0	B#16#00					
14.0	MDS_Status0.reserved1[3]	BYTE	B#16#0	B#16#00					
15.0	MDS_Status0.reserved1[4]	BYTE	B#16#0	B#16#00					
16.0	MDS_Status0.reserved1[5]	BYTE	B#16#0	B#16#00					
17.0	MDS_Status0.reserved1[6]	BYTE	B#16#0	B#16#00					
18.0	MDS_Status1.reserved0	BYTE	B#16#0	B#16#02					
19.0	MDS_Statusl.status_info	BYTE	B#16#0	B#16#00	Modus MDS-Status				
20.0	MDS_Status1.UID[1].Byte_1_4	DWORD	DW#16#0	DW#16#00000000	MDS-Nummer (unique identifier)				
24.0	MDS_Status1.UID[1].Byte_5_8	DWORD	DW#16#0	DW#16#557BA57F					
28.0	MDS_Status1.LFD	BYTE	B#16#0	B#16#0D	Leistungsflussdichte: Beziehung zwischen Grenzwert um				
29.0	MDS_Status1.FZP	BYTE	B#16#0	B#16#00	Fehlerzähler passiv (Ruhefehlerzähler)				
30.0	MDS_Status1.FZA	BYTE	B#16#0	B#16#03	Fehlerzähler aktiv (Fehler während Kommunikation)				
31.0	MDS_Status1.ANWZ	BYTE	B#16#0	B#16#FF	Anwesenheitszähler				
32.0	MDS_Status1.reserved1[1]	BYTE	B#16#0	B#16#00					
33.0	MDS_Status1.reserved1[2]	BYTE	B#16#0	B#16#00					
34.0	MDS Status1.reserved1[3]	BYTE	B#16#0	B#16#00					